

pfSense 2 Cookbook

A practical, example-driven guide to configure even the most advanced features of pfSense 2

Matt Williamson

[PACKT] open source 
PUBLISHING community experience distilled
BIRMINGHAM - MUMBAI

pfSense 2 Cookbook

Copyright © 2011 Packt Publishing

All rights reserved. No part of this book may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, without the prior written permission of the publisher, except in the case of brief quotations embedded in critical articles or reviews.

Every effort has been made in the preparation of this book to ensure the accuracy of the information presented. However, the information contained in this book is sold without warranty, either express or implied. Neither the author nor Packt Publishing, and its dealers and distributors will be held liable for any damages caused or alleged to be caused directly or indirectly by this book.

Packt Publishing has endeavored to provide trademark information about all of the companies and products mentioned in this book by the appropriate use of capitals. However, Packt Publishing cannot guarantee the accuracy of this information.

First published: March 2011

Production Reference: 1180311

Published by Packt Publishing Ltd.
32 Lincoln Road
Olton
Birmingham, B27 6PA, UK.

ISBN 978-1-849514-86-6

www.packtpub.com

Cover Image by Asher Wishkerman (a.wishkerman@mpic.de)

About the Reviewers

Josh Brower has been working in IT since he crashed his first computer at age 14. He writes blogs regularly at <http://defensivedepth.com/> on a variety of Information Security topics. He is currently working with a non-profit organization as the head of IT Security, and pursuing his graduation degree in Information Security from STI. Josh is happily married to his wife Mandi. They have one son.

Jim Cheetham has been managing, deploying, supporting, and designing Unix solutions and TCP/IP networks for over 20 years. During this time, he has been part of the establishment of the first SSL-protected website outside the USA, the design and implementation of a high-volume web portal that deliberately had no firewalls between it and the Internet, and has run a busy Managed Network and Security Service looking after multiple government departments.

Jim has worked for global companies such as ICL, Vodafone, and Unisys, along with keeping hands-on with numerous small, interesting, and fast-moving businesses. Jim is currently running Inode Ltd., a New Zealand-based consultancy and service provider specializing in open source solutions for management of networks, systems, and security.

I'd like to thank my wife Maria and my children Alexander and Katherine for letting me spend so much time behind the keyboard hacking, and for keeping things running smoothly at home when I have to take trips away for work.

Brad Hedlund is a Technical Solutions Architect at Cisco Systems, Inc. in the company's Center of Excellence for Data Center field sales. Since joining Cisco in 2006, Brad has been helping Enterprise customers design large and small data centers with challenging and complex requirements. Brad has extensive design experience with Cisco's Data Center switching line (Nexus) and Cisco's Unified Computing System (UCS), with specific expertise in server networking and virtualization. Brad Hedlund also maintains a popular blog on data center networking topics at <http://bradhedlund.com>.

Mohd Izhar Bin Ali, CEH CHFI is an independent security consultant having 10 years' working experience in networking, open source, and the IT Security field. He started his career as a Security Analyst with SCAN Associates, Berhad, and he is one of the team members managing the security services of an Intrusion Detection System (IDS) for Malaysian government's SOC center. After that, he became a trainer (LINUX and Networking) for the largest private education college in Malaysia. Before becoming a freelance security consultant, he worked with FIRMUS Security Sdn Bhd, one of the largest IT security companies in Malaysia. With FIRMUS, he had performed enterprise security assessment to clients (banking, insurance, and government) including web penetration testing, external and internal penetration testing, and wireless penetration testing. Now, takes up freelance jobs in security and also research in the network security field.

He has contributed articles on pfSense (*Setup Squid as A Transparent Proxy*, *Setup VideoCache with Squid*) and has also written white papers for The Exploit Database (MySQL Injection using `darkMySQLi.py`, Howto: DNS Enumeration, Easy Method: Blind SQL Injection).

I would like to thank Allah, my parents, my girlfriend Umairah, and also my best friend in IT security, Mohd Asrullita bin Abdul Taib.

Table of Contents

Preface	<u>1</u>
Chapter 1: Initial Configuration	<u>1</u>
Introduction	1
Applying basic settings in General Setup	2
Identifying and assigning interfaces	4
Configuring the WAN interface	6
Configuring the LAN interface	9
Configuring optional interfaces	11
Enabling the Secure Shell (SSH)	14
Generating authorized RSA keys	15
Configuring SSH RSA key authentication	18
Accessing the Secure Shell (SSH)	19
Chapter 2: Essential Services	<u>23</u>
Introduction	23
Configuring the DHCP server	24
Creating static DHCP mappings	26
Configuring the DHCP relay	28
Specifying alternate DNS servers	31
Configuring the DNS Forwarder	32
Configuring a standalone DHCP/DNS server	35
Configuring dynamic DNS	38
Chapter 3: General Configuration	<u>41</u>
Introduction	41
Creating an alias	41
Creating a NAT port forward rule	47
Creating a firewall rule	51
Creating a schedule	57
Remote desktop access, a complete example	61

Chapter 4: Virtual Private Networking	67
Introduction	67
Creating an IPsec VPN tunnel	68
Configuring the L2TP VPN service	70
Configuring the OpenVPN service	76
Configuring the PPTP VPN service	82
Chapter 5: Advanced Configuration	93
Introduction	93
Creating a virtual IP	94
Configuring a 1:1 NAT rule	99
Creating an outbound NAT rule	102
Creating a gateway	106
Creating a static route	109
Configuring traffic-shaping (QoS, Quality of Service)	111
Bridging interfaces	116
Creating a virtual LAN	118
Creating a captive portal	119
Chapter 6: Redundancy, Load Balancing, and Failover	125
Introduction	125
Configuring multiple WAN interfaces	126
Configuring multi-WAN load balancing	131
Configuring multi-WAN failover	134
Configuring a web server load balancer	138
Configuring a web server failover	141
Configuring CARP firewall failover	145
Chapter 7: Services and Maintenance	153
Introduction	154
Enabling OLSR	154
Enabling PPPoE	156
Enabling RIP	158
Enabling SNMP	159
Enabling UPnP and NAT-PMP	161
Enabling OpenNTPD	164
Enabling Wake On LAN (WOL)	165
Enabling external logging (syslog server)	168
Using ping	170
Using traceroute	172
Backing up the configuration file	174
Restoring the configuration file	176
Configuring automatic configuration file backup	179

Updating pfSense firmware	181
Appendix A: Monitoring and Logging	187
Introduction	187
Customizing the Status Dashboard	187
Monitoring current traffic	190
Configuring SMTP e-mail notifications	191
Viewing system logs	192
Configuring an external syslog server	195
Viewing RRD graphs	197
Viewing DHCP leases	202
Managing services	204
Monitoring the packet filter with pfInfo	206
Monitoring traffic with pfTop	207
Monitoring system activity	209
Appendix B: Determining our Hardware Requirements	211
Introduction	211
Determining our deployment scenario	212
Determining our throughput requirements	214
Determining our interface requirements	217
Choosing a standard or embedded Image	219
Choosing a Form Factor	220
Index	225

Preface

pfSense is an open source distribution of FreeBSD-based firewall which provides a platform for flexible and powerful routing and firewalling. The versatility of pfSense presents us with a wide array of configuration options which, compared to other offerings, makes determining requirements a little more difficult and a lot more important. Through this book, you will see that pfSense offers numerous other alternatives to fit any environment's security needs.

This book follows a cookbook style to teach you how to use the features available with pfSense after determining your environment's security requirements. It covers everything from initial configuration of your network interfaces and pfSense services such as DHCP and Dynamic DNS to complex techniques to enable failover and load-balancing.

What this book covers

Chapter 1, Initial Configuration covers the settings needed for almost every pfSense deployment including those for a firewall, router, and wireless access point. Through the recipes in this chapter, you will learn how to install and configure pfSense with a fully-operational firewall and router.

Chapter 2, Essential Services explains how to configure the essential networking services provided by pfSense such as the DHCP server and dynamic DNS services.

Chapter 3, General Configuration describes how to configure NAT and firewall rules and the features associated with them.

Chapter 4, Virtual Private Networking describes how to configure pfSense to serve any or all of the four major VPN implementations—IPSec, L2TP, OpenVPN, and PPTP.

Chapter 5, Advanced Configuration covers advanced networking features such as configuring different types of virtual IP, creating gateways, and bridging interfaces.

Chapter 6, Redundancy, Load Balancing, and Failover contains recipes explaining how to load-balance or failover the multi-WAN interfaces to protect large and sensitive systems.

Chapter 7, Services and Maintenance describes all the networking services and features offered in pfSense such as configuring external logging (syslog server), enabling Wake On LAN (WOL), and configuring automatic configuration file backup.

Appendix A, Monitoring and Logging includes the features available in pfSense to help you monitor your system and also covers how to use different logging tools built into pfSense.

Appendix B, Determining our Hardware Requirements will show you how to choose the best pfSense configuration after you determine your firewall requirements. You will even learn how and where to deploy pfSense to fit your environment's security needs.

What you need for this book

A working installation of pfSense 2.0 is the only requirement for the recipes in this book. Readers who are new to pfSense can follow the recipes in the appendices for instructions on how to determine what type of hardware they should install pfSense on. The minimum requirements for a pfSense installation are 500Mhz, 128MB RAM, and 1GB hard disk space. PfSense can also be installed as a virtual machine, and for convenience a VMWare image is available from the **Downloads** section of the pfSense website.

Who this book is for

This book is intended for all levels of network administrators. If you are an advanced user of pfSense, then you can flip to a particular recipe and quickly accomplish the task at hand, while if you are new to pfSense, you can read chapter-by-chapter and learn all of the features of the system from the ground-up.

Conventions



In this book, you will find a number of styles of text that distinguish between different kinds of information. Here are some examples of these styles, and an explanation of their meaning.

Code words in text are shown as follows: "Our public key is now located at `/home/user/.ssh/id_rsa.pub`."

Any command-line input **or** output is written as follows:

```
ssh -i /home/matt/key/id_rsa admin@192.168.1.1
```

New terms and **important words** are shown in bold. Words that you see on the screen, in menus or dialog boxes for example, appear in the text like this: "On the **Virtual IPs** tab, click the "plus" button to add a new virtual IP Address".



Reader feedback

Feedback from our readers is always welcome. Let us know what you think about this book—what you liked or may have disliked. Reader feedback is important for us to develop titles that you really get the most out of.

To send us general feedback, simply send an e-mail to feedback@packtpub.com, and mention the book title via the subject of your message.

If there is a book that you need and would like to see us publish, please send us a note in the **SUGGEST A TITLE** form on www.packtpub.com or e-mail suggest@packtpub.com.

If there is a topic that you have expertise in and you are interested in either writing or contributing to a book, see our author guide on www.packtpub.com/authors.

Customer support

Now that you are the proud owner of a Packt book, we have a number of things to help you to get the most from your purchase.

Errata

Although we have taken every care to ensure the accuracy of our content, mistakes do happen. If you find a mistake in one of our books—maybe a mistake in the text or the code—we would be grateful if you would report this to us. By doing so, you can save other readers from frustration and help us improve subsequent versions of this book. If you find any errata, please report them by visiting <http://www.packtpub.com/support>, selecting your book, clicking on the **errata submission form** link, and entering the details of your errata. Once your errata are verified, your submission will be accepted and the errata will be uploaded on our website, or added to any list of existing errata, under the Errata section of that title. Any existing errata can be viewed by selecting your title from <http://www.packtpub.com/support>.

Piracy

Piracy of copyright material on the Internet is an ongoing problem across all media. At Packt, we take the protection of our copyright and licenses very seriously. If you come across any illegal copies of our works, in any form, on the Internet, please provide us with the location address or website name immediately so that we can pursue a remedy.

Please contact us at copyright@packtpub.com with a link to the suspected pirated material.

We appreciate your help in protecting our authors, and our ability to bring you valuable content.

Questions

You can contact us at questions@packtpub.com if you are having a problem with any aspect of the book, and we will do our best to address it.

1

Initial Configuration

In this chapter, we will cover:

- ▶ Applying basic settings in General Setup
- ▶ Identifying and assigning interfaces
- ▶ Configuring the WAN interface
- ▶ Configuring the LAN interface
- ▶ Configuring optional interfaces
- ▶ Enabling the Secure Shell (SSH)
- ▶ Generating authorized RSA keys
- ▶ Configuring SSH RSA key authentication
- ▶ Accessing the Secure Shell (SSH)

Introduction

PfSense is an open source operating system used to turn a computer into a firewall, router, or a variety of other application-specific network appliances. PfSense is a customized FreeBSD distribution based on the **m0n0wall project**, a powerful but light-weight firewall distribution. PfSense builds upon m0n0wall's foundation and takes its functionality several steps further by adding a variety of other popular networking services.

This chapter covers the core settings needed for almost every pfSense deployment; whether that is a firewall, router, or even a wireless access point! Once pfSense is installed and configured according to the recipes in this chapter, you will have a fully-operation firewall plus router. At its most basic level, a pfSense machine can be used to replace the common home router when more functionality is desired. In more advanced configurations, pfSense can be used to establish a secure tunnel to a remote office, load-balance a web farm, or shape and prioritize all network traffic just to name a few example scenarios. There are literally hundreds of ways to configure and customize a pfSense installation.

Once pfSense is installed, there are two ways to access the system remotely—SSH and the WebGUI. An SSH connection will present you with the same low-level system menu that you would see on the screen if your machine is connected to a monitor. The SSH menu options are basic and very little configuration is done here. The entire configuration described in every recipe in this book is done through the WebGUI interface, unless specified otherwise, which is accessible through the IP address of any interface you configured during installation (such as 192.168.1.1).

Applying basic settings in General Setup

This recipe describes how to configure the core system settings in PfSense.

Getting ready

All that's required for this recipe is a base installation of pfSense and access to the WebGUI. Some of these settings will have been configured during the installation process, but can be modified here at any time.



On a new install, the default credentials are:

Username: admin


Password: pfsense

How to do it...

1. Browse to **System | General Setup**.
2. Enter a **Hostname**. This name will be used to access the machine by name instead of the IP address. For example, we can browse to `http://pfsense` instead of `http://192.168.1.1`.





System	
Hostname	<div> pfsense</div> <div>Name of the firewall host, without domain part e.g. <i>firewall</i></div>

3. Enter your **Domain**:

Domain	<div> example.com</div> <div>Do not use 'local' as a domain name. It will cause local hosts running mDNS (avahi, bonjour, etc.) to be unable to resolve local hosts not running mDNS. e.g. <i>mycorp.com, home, office, private, etc.</i></div>
--------	--

4. **DNS Servers** can be specified here. By default, pfSense will act as the primary DNS server and these fields will be blank. However, other DNS servers may certainly be used. Please refer to the *Specifying alternate DNS servers* recipe in *Chapter 2, Essential Services* for more information.

DNS servers

DNS Server	Use gateway
 <input type="text"/>	None ▼
 <input type="text"/>	None ▼
 <input type="text"/>	None ▼
 <input type="text"/>	None ▼

IP addresses: these are also used for the DHCP service, DNS forwarder and for PPTP VPN clients.


In addition, select the gateway for each DNS server. You should have a unique DNS server per gateway.

5. Check **Allow DNS server list to be overridden by DHCP/PPP on WAN**. This ensures that any DNS requests that can't be resolved internally are passed on and resolved by the external DNS servers provided by your ISP.

☒ **Allow DNS server list to be overridden by DHCP/PPP on WAN**
 If this option is set, pfSense will use DNS servers assigned by a DHCP/PPP server on WAN for its own purposes (including the DNS forwarder). However, they will not be assigned to DHCP and PPTP VPN clients.

6. Enter a **Time zone** and leave the default **NTP time server** as **0.pfsense.pool.ntp.org**.

Time zone ▼
 Select the location closest to you

NTP time server 
 Use a space to separate multiple hosts (only one required). Remember to set up at least one DNS server if you enter a host name here!

7. I'd recommend the default **Theme**, pfSense 2.0's new **pfsense_ng**. The top menus are now static and won't disappear if you scroll down through the content of the page, a great addition to the UI.

Theme

▼ **This will change the look and feel of pfSense.**

See also

- ▶ The *Configuring the DNS Forwarder* recipe in *Chapter 2, Essential Services*
- ▶ The *Specifying alternate DNS servers* recipe in *Chapter 2, Essential Services*

Identifying and assigning interfaces

This recipe describes how to identify a network configuration and assign the appropriate interfaces in pfSense.

Getting ready

You'll need to identify the MAC address for each Ethernet port on your pfSense machine before attempting to assign interfaces.

How to do it...

1. Access the console from the physical machine or enable SSH and connect remotely (see the *Enabling the Secure Shell (SSH)* recipe for details).
2. The home screen will display a list of interfaces, network ports, and IP addresses:

```
matt@thinkpad:~$ ssh admin@192.168.1.1
Password:
*** Welcome to pfSense 2.0-BETA5-nanobsd (i386) on pfsense ***

WAN (wan)          -> fxp0          -> [REDACTED] (DHCP)
LAN (lan)           -> em0           -> 192.168.1.1
OPT1 (opt1)         -> em1           -> NONE

0) Logout (SSH only)      8) Shell
1) Assign Interfaces      9) pfTop
2) Set interface(s) IP address
3) Reset webConfigurator password
4) Reset to factory defaults
5) Reboot system
6) Halt system
7) Ping host
10) Filter Logs
11) Restart webConfigurator
12) pfSense Developer Shell
13) Upgrade from console
14) Disable Secure Shell (sshd)

Enter an option: █
```

3. Choose option **1** to **Assign Interfaces**.
4. Skip setting up VLANs for now. See the *Creating a Virtual LAN* recipe in *Chapter 5, Essential Services* for more information.

```

Enter an option: 1

Valid interfaces are:

em0  00:90:0b:12:01:52  (up)  Intel(R) PRO/1000 Network Connection 7.1.8
em1  00:90:0b:12:01:51  (down) Intel(R) PRO/1000 Network Connection 7.1.8
em2  00:90:0b:12:01:50  (down) Intel(R) PRO/1000 Network Connection 7.1.8
em3  00:90:0b:12:01:4f  (down) Intel(R) PRO/1000 Network Connection 7.1.8
fxp0 00:90:0b:12:01:53  (up)  Intel 82562ET/EZ/GT/GZ PRO/100 VE Ethernet

Do you want to set up VLANs first?

If you are not going to use VLANs, or only for optional interfaces, you should
say no here and use the webConfigurator to configure VLANs later, if required.

Do you want to set up VLANs now [y|n]? n

```

5. Assign each interface to the interface of your choice by matching the MAC address to the interface address on the display:

```

*NOTE* pfSense requires *AT LEAST* 1 assigned interfaces to function.
If you do not have *AT LEAST* 1 interfaces you CANNOT continue.

If you do not have at least 1 *REAL* network interface cards
or one interface with multiple VLANs then pfSense
*WILL NOT* function correctly.

If you do not know the names of your interfaces, you may choose to use
auto-detection. In that case, disconnect all interfaces now before
hitting 'a' to initiate auto detection.

Enter the WAN interface name or 'a' for auto-detection: fxp0

Enter the LAN interface name or 'a' for auto-detection
NOTE: this enables full Firewalling/NAT mode.
(or nothing if finished): em0

Optional interface 1 description found: OPT1
Enter the Optional 1 interface name or 'a' for auto-detection
(or nothing if finished): em1

Enter the Optional 2 interface name or 'a' for auto-detection
(or nothing if finished):

The interfaces will be assigned as follows:

LAN -> em0
WAN -> fxp0
OPT1 -> em1

Do you want to proceed [y|n]? y

Writing configuration...done.

```



The ability to only configure a single interface is new to pfSense 2.0. Prior versions required a minimum of two (WAN and LAN) interfaces.

How it works...

pfSense, like any other computer operating system, references each NIC by some unique value (*fxp0*, *em0*, *em1*, and so on). These unique identifiers are often associated with the driver being used and make it easier for us humans to use than the associated MAC address (00:80:0c:12:01:52). Taking that concept a step further, an interface is simply a named placeholder for each port: *fxp0*=WAN, *em0*=LAN, *em1*=DMZ, and so on.

There's more...

Now that you know which port is mapped to which interface, you can manage future interface changes through the WebGUI by browsing to **Interfaces | (assign)**.

Interfaces: Assign network ports

Interface assignments | Interface Groups | Wireless | VLANs | QinQs | PPPs | GRE | GIF | Bridges | LAGG

Interface	Network port
WAN	fxp0 (00:90:0b:12:01:53) ▼
LAN	em0 (00:90:0b:12:01:52) ▼
OPT1	em1 (00:90:0b:12:01:51) ▼

See also

- ▶ The *Accessing the Secure Shell (SSH)* recipe
- ▶ The *Configuring the WAN interface* recipe
- ▶ The *Configuring the LAN interface* recipe
- ▶ The *Configuring optional interfaces* recipe

Configuring the WAN interface


This recipe describes how to configure the **Wide Area Network (WAN)** on the external interface of our firewall.

Getting ready

The WAN interface is your connection to the outside world. You'll need a properly configured WAN interface (as described in the previous chapter) and an Internet connection. In this example, a cable modem provides the Internet connection from our local **Internet Service Provider (ISP)**, but pfSense will support every other major connection method.

How to do it...

1. Browse to **Interfaces | WAN**.
2. Check **Enable Interface**.
3. Choose an address configuration **Type**.
4. Leave **MAC address** blank. Manually entering a MAC address here is known as "spoofing". Your ISP has no way of verifying MAC addresses, so you can simply make one up. This can be helpful if you're trying to force your ISP to hand you a new IP address or a different set of DNS servers.
5. Leave **MTU**, **MSS**, **Hostname**, and **Alias IP address** blank.

General configuration	
Enable	<input checked="" type="checkbox"/> Enable Interface
Description	 WAN Enter a description (name) for the interface here.
Type	DHCP ▼
MAC address	 <input type="text"/> <small>Insert my local MAC address</small> This field can be used to modify ("spoof") the MAC address of the WAN interface (may be required with some cable connections) Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx or leave blank
MTU	 <input type="text"/> If you leave this field blank, the adapter's default MTU will be used. This is typically 1500 bytes but can vary on some hardware.
MSS	 <input type="text"/> If you enter a value in this field, then MSS clamping for TCP connections to the value entered above minus 40 (TCP/IP header size) will be in effect.
DHCP client configuration	
Hostname	 <input type="text"/> The value in this field is sent as the DHCP client identifier and hostname when requesting a DHCP lease. Some ISPs may require this (for client identification).
Alias IP address	 <input type="text"/> 32 ▼ The value in this field is used as a fixed alias IP address by the DHCP client.

6. Check **Block private networks**. This setting is usually only checked on a WAN interface.
7. Check **Block bogon networks**. This setting is usually only checked on a WAN interface.
8. **Save** changes.

Private networks

☒ **Block private networks**
When set, this option blocks traffic from IP addresses that are reserved for private networks as per RFC 1918 (10/8, 172.16/12, 192.168/16) as well as loopback addresses (127/8). You should generally leave this option turned on, unless your WAN network lies in such a private address space, too.

☒ **Block bogon networks**
When set, this option blocks traffic from IP addresses that are reserved (but not RFC 1918) or not yet assigned by IANA. Bogons are prefixes that should never appear in the Internet routing table, and obviously should not appear as the source address in any packets you receive.

Save **Cancel**

How it works...

We must first establish our connection to the Internet before we can configure pfSense to allow our other networks to access it. The example we've performed is typical of many SOHO environments. By placing our firewall as the only machine with direct access to the Internet, we are securing our environment by establishing complete control over the traffic that flows in and out of our networks. All traffic must now pass through our firewall and abide by our rules.

There's more...

We can now connect our WAN device (cable modem) to the WAN Ethernet port we've defined on our pfSense box. Once the connection has been established, we can check the status of our WAN port from **Status | Interfaces**:

Status: Interfaces ?	
WAN interface (fxp0)	
Status	up
DHCP	up <input type="button" value="Release"/>
MAC address	00:90:0b:12:01:53
IP address	
Subnet mask	255.255.254.0
Gateway	CW_WAN
ISP DNS servers	
Media	100baseTX <full-duplex>
In/out packets	158488436/157239137 (72.99 GB/164.77 GB)
In/out packets (pass)	157239137/181687613 (72.86 GB/164.77 GB)
In/out packets (block)	1249299/0 (135.75 MB/0 bytes)
In/out errors	0/0
Collisions	0

See also

- ▶ The *Identifying and assigning interfaces* recipe
- ▶ The *Configuring the LAN interface* recipe
- ▶ The *Configuring optional interfaces* recipe

Configuring the LAN interface

This recipe describes how to configure the **Local Area Network (LAN)** internal interface of our firewall.

Getting ready

The LAN interface is used to connect your devices to a secure internal network. A properly configured LAN interface is required.

How to do it...

1. Browse to **Interfaces | LAN**.
2. Check **Enable Interface**.
3. Choose an address configuration **Type**.

4. Enter an **IP address** and subnet mask. Leave **Gateway** set to **None**.

General configuration	
Enable	<input checked="" type="checkbox"/> Enable Interface
Description	LAN Enter a description (name) for the interface here.
Type	Static ▼
MAC address	<input type="text"/> Insert my local MAC address This field can be used to modify ("spoof") the MAC address of the WAN interface (may be required with some cable connections) Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx or leave blank
MTU	<input type="text"/> If you leave this field blank, the adapter's default MTU will be used. This is typically 1500 bytes but can vary on some hardware.
MSS	<input type="text"/> If you enter a value in this field, then MSS clamping for TCP connections to the value entered above minus 40 (TCP/IP header size) will be in effect.
Static IP configuration	
IP address	192.168.1.1 / 24 ▼
Gateway	None ▼ If this interface is an Internet connection, select an existing Gateway from the list or add a new one.

5. Ensure **Block private networks** and **Block bogon networks** are **unchecked**.
6. **Save** the changes.

Private networks
<input type="checkbox"/> Block private networks When set, this option blocks traffic from IP addresses that are reserved for private networks as per RFC 1918 (10/8, 172.16/12, 192.168/16) as well as loopback addresses (127/8). You should generally leave this option turned on, unless your WAN network lies in such a private address space, too.
<input type="checkbox"/> Block bogon networks When set, this option blocks traffic from IP addresses that are reserved (but not RFC 1918) or not yet assigned by IANA. Bogons are prefixes that should never appear in the Internet routing table, and obviously should not appear as the source address in any packets you receive.
<div>Save Cancel</div>

How it works...

You've just defined your first internal network. If you've been performing the recipes in order, you've now met the minimum requirements for a fully-functioning firewall! You've defined one external network (WAN) and one internal network (LAN). You can now define the rules and relationships to regulate traffic between the two.

There's more...

You can now connect a switch to the LAN interface on your pfSense machine. This will allow you to connect multiple computers to your LAN network.

See also

- ▶ The *Identifying and assigning interfaces* recipe
- ▶ The *Configuring the WAN interfaces* recipe
- ▶ The *Configuring optional interfaces* recipe

Configuring optional interfaces

This recipe describes how to create and assign optional network interfaces to our firewall.

Getting ready

The optional network you'll create in this example is commonly referred to as a DMZ. The idea is taken from the military concept of a de-militarized zone, in which some traffic is allowed to pass and some traffic isn't. The idea is that the area is controlled and clearly separate from your other areas. When applied to networking, a DMZ network follows this pattern:

Internet Traffic | ← DMZ ← LAN Traffic

Unsafe Internet traffic is allowed to enter the DMZ, to access a webserver for example. LAN traffic can also enter the DMZ; it wants to access the webserver too. However, the key lies in the last rule—no DMZ traffic is allowed to enter the LAN.

The DMZ network is our less secure network we'll allow certain external access to. To configure a DMZ, or any other optional network, we'll need an available interface.

How to do it...

1. Browse to an available interface, **Interfaces** | **OPT1**.
2. Check **Enable Interface**.
3. Set **Description** to **DMZ**.
4. Choose an address configuration **Type**, **Static** for our example.
5. Enter an **IP address** and the subnet mask. We'll use **192.168.2.1** and select **24** from the drop-down list.

6. Leave **Gateway** set to **None**.

General configuration	
Enable	<input checked="" type="checkbox"/> Enable Interface
Description	<input type="text" value="DMZ"/> Enter a description (name) for the interface here.
Type	Static ▾
MAC address	<input type="text"/> Insert my local MAC address This field can be used to modify ("spoof") the MAC address of the WAN interface (may be required with some cable connections) Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx or leave blank
MTU	<input type="text"/> If you leave this field blank, the adapter's default MTU will be used. This is typically 1500 bytes but can vary on some hardware.
MSS	<input type="text"/> If you enter a value in this field, then MSS damping for TCP connections to the value entered above minus 40 (TCP/IP header size) will be in effect.
Static IP configuration	
IP address	<input type="text" value="192.168.2.1"/> / <input type="text" value="24"/> ▾
Gateway	None ▾ If this interface is an Internet connection, select an existing Gateway from the list or add a new one.

7. Ensure **Block private networks** and **Block bogon networks** are unchecked.
8. **Save** the changes.

Private networks	
<input type="checkbox"/> Block private networks	When set, this option blocks traffic from IP addresses that are reserved for private networks as per RFC 1918 (10/8, 172.16/12, 192.168/16) as well as loopback addresses (127/8). You should generally leave this option turned on, unless your WAN network lies in such a private address space, too.
<input type="checkbox"/> Block bogon networks	When set, this option blocks traffic from IP addresses that are reserved (but not RFC 1918) or not yet assigned by IANA. Bogons are prefixes that should never appear in the Internet routing table, and obviously should not appear as the source address in any packets you receive.
<input type="button" value="Save"/> <input type="button" value="Cancel"/>	


9. **Apply** changes.

How it works...

Your DMZ network will allow external (WAN) access. Your DMZ will also allow access from the LAN, but it won't be permitted to send traffic to the LAN. This will allow devices on the Internet to access your DMZ resources (websites, e-mail, and so on) without being able to access any part of your private LAN network.

There's more...

You could now attach a switch to your DMZ interface to connect multiple machines. If you've been following these recipes in order, a diagram of your network would look something like this:



See also

- ▶ The *Identifying and assigning interfaces* recipe
- ▶ The *Configuring the WAN interface* recipe
- ▶ The *Configuring the LAN interface* recipe

Enabling the Secure Shell (SSH)

This recipe describes how to enable the Secure Shell (SSH) service in pfSense.

Getting ready

SSH is a networking protocol that allows encrypted communication between two devices. Enabling SSH allows secure access to the pfSense console remotely, just as if you were sitting in front of the physical console.

How to do it...

1. Browse to **System | Advanced | Secure Shell**.
2. Check **Enable Secure Shell**.
3. You will be prompted for credentials when you connect (use the same username and password as the webGUI), but checking **Disable password login for Secure Shell** will allow you to use RSA keys instead. See the next recipe for details.
4. Leave the **SSH port** blank to use the default port:

Secure Shell	
Secure Shell Server	<input checked="" type="checkbox"/> Enable Secure Shell
Authentication Method	<input type="checkbox"/> Disable password login for Secure Shell (RSA key only) <small>When enabled, authorized keys need to be configured for each user that has been granted secure shell access.</small>
SSH port	<input type="text"/> <small>Note: Leave this blank for the default of 22.</small>

5. **Save** the changes and the SSH service will be started.

How it works...

Enabling the Secure Shell turns on pfSense's built-in SSH server to listen to requests on the port you've specified (port 22 by default).



Like all pfSense services (unless otherwise noted), the SSH service will listen on every available interface. Like other services, firewall's rules are used to grant or deny access to these services. See *Chapter 3, General Configuration* for more information on configuring firewall rules.

There's more...

Changing the SSH authentication method to use RSA keys is a great way to secure access to your system. See the following recipe for details.

Additionally, you can change the port that SSH listens on. Doing so may increase security slightly by reducing the number of unauthorized login attempts, but you will need to remember what you have changed it to, or you will be unable to connect.

See also

- ▶ The *Generating authorized RSA keys* recipe
- ▶ The *Creating a firewall rule* recipe in *Chapter 3, General Configuration*

Generating authorized RSA keys

This recipe describes how to create an authorized RSA key so a user can connect to pfSense without being prompted for a password.

Getting ready


Linux and Mac users will need to ensure **ssh-keygen** is installed on their system (almost all distributions have this installed by default). Windows users will need to download and install the **PuTTYGen** tool.

How to do it...

Generate an SSH key from a Linux/Mac Client as follows:

1. Open a terminal and run:
ssh-keygen
2. Save the key to the default location of `/home/user/.ssh/` and specify a pass code (optional, but recommended).

3. Your public key is now located at `/home/user/.ssh/id_rsa.pub`.




```

matt@thinkpad: ~
matt@thinkpad:~$ ssh-keygen
Generating public/private rsa key pair.
Enter file in which to save the key (/home/matt/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /home/matt/.ssh/id_rsa.
Your public key has been saved in /home/matt/.ssh/id_rsa.pub.
The key fingerprint is:
21:34:73:68:8a:f2:e4:ec:14:81:90:47:b4:0b:1f:1d matt@thinkpad
The key's randomart image is:
+--[ RSA 2048 ]-----+
|o=o E +..|
|o oo oo+|
|..oo.o. |
|.O+o. . |
|*o. S |
|= |
|o |
|. |
+-----+
matt@thinkpad:~$


```

Generate an SSH key from a Windows client using PuTTY as follows:

4. Open PuTTYGen and generate a public/private key pair by clicking the **Generate** button.
5. Enter a passphrase (optional, but recommended).
6. Click the **Save Private Key** button and choose a location, such as `C:\MyPrivateKey.ppk`.



7. Highlight the public key that was generated in the textbox and copy and paste it into a new file, let's say `C:\MyPublicKey.txt`. (Do not use the **Save Public Key** button, as that adds comments and other fields that are sometimes incompatible.)



How it works...

RSA keys have become a standard for securing client/server connections for any service which chooses to take advantage of it. A client generates a key pair—a private key file and a public key file (an optional pass-phrase can be specified for enhanced security). Now, any server administrator can request that client's public key and add it to their system. The client can then securely authenticate without typing in a password.

There's more...

RSA key authentication is most often associated with SSH access, and is often referred to as SSH keys but that is misleading. RSA keys are generic and not specific to SSH. Although SSH often uses them, RSA keys can be used by any type of service that chooses to support them, such as VPN, VoIP, FTP, and so on.

See also

- ▶ *The Enabling the Secure Shell (SSH) recipe*
- ▶ *The Configuring SSH RSA key authentication recipe*

Configuring SSH RSA key authentication

This recipe describes how to configure pfSense to use an RSA key rather than a password for SSH authentication.

Getting ready


Make sure that SSH is already enabled and you have generated a public key for your client.

How to do it...

1. Browse to **System | Advanced | Secure Shell**.
2. Check **Disable password login for Secure Shell (RSA key only)**.

Secure Shell	
Secure Shell Server	<input checked="" type="checkbox"/> Enable Secure Shell
Authentication Method	<input checked="" type="checkbox"/> Disable password login for Secure Shell (RSA key only) When enabled, authorized keys need to be configured for each user that has been granted secure shell access.
SSH port	<input type="text"/> Note: Leave this blank for the default of 22.

3. Edit the user we will associate with the client's public key from **System | User Manager | Edit admin**.
4. Select **Click to paste an authorized key** and paste our client's public RSA key here. When pasted, the key should appear as a single line. Be sure your text editor didn't insert any line feed characters or authentication may fail.

Authorized keys	<div> ssh-rsa AAAAB3NzaC1yc2EAAAABIwAAAQEA8XhC3bjKxapgtA6bxH1EJ6pgPNphDwo: <div><div></div></div></div> <div>Paste an authorized keys file here.</div>
-----------------	---

5. **Save** the changes.

How it works...

When we connect using an SSH client, we won't be asked for a password. Instead, the SSH server will use its copy of the public RSA key to send a challenge that can only be read if you possess the matching private key.

There's more...

RSA private keys can also be stored encrypted on the client machine. The SSH client will prompt for a decryption passphrase for the private key before being able to use it for authentication with the server.

See also

- ▶ The Enabling the Secure Shell (SSH) recipe
- ▶ The Generating authorized RSA keys recipe
- ▶ The Accessing the Secure Shell (SSH) recipe

Accessing the Secure Shell (SSH)

This recipe describes how to access the pfSense console from any Linux, Mac, or Windows client computer.

Getting ready

SSH must be enabled and configured on our pfSense box. Linux and Mac users will have the SSH client installed by default. Windows users will have to download and install **PuTTY**.

How to do it...

Connect via SSH from a Linux/Mac client as follows:

1. Open a terminal window and run:
2. If you are using the default configuration, you'll then be prompted for a password.
3. If you are using RSA key authentication, you'll connect directly or be asked to enter the pass-phrase associated with your key. If you need to specify the location of your private key file, you can use the `-i` option as follows:


```
ssh -i /home/matt/key/id_rsa admin@192.168.1.1
```

4. If you've configured pfSense to use a different port, you can specify that using the `-p` option, as in the following example:

```
ssh -p 12345 admin@192.168.1.1
```

Connect via SSH from a Windows client with PuTTY as follows:

5. Open PuTTY and specify your hostname or IP address.
6. Specify an alternative port if necessary (default is port 22).
7. If you are using RSA key authentication, browse to your private key file from **Connection | SSH | Auth | Private key file for authentication**.



8. You'll connect and be prompted for a username.
9. You'll then be prompted for a password, or if RSA authentication is used, you'll connect directly or be prompted for your pass-phrase.

How it works...

SSH allows access to the pfSense console menu from any computer that has an SSH client. You can even access the console from your phone if you install an SSH client on your mobile device.

See also

- ▶ The *Enabling the Secure Shell (SSH)* recipe
- ▶ The *Generating authorized RSA keys* recipe
- ▶ The *Configuring SSH RSA key authentication* recipe

2

Essential Services

In this chapter, we will cover:

- ▶ Configuring the DHCP server
- ▶ Creating static DHCP mappings
- ▶ Configuring the DHCP relay
- ▶ Specifying alternate DNS servers
- ▶ Configuring the DNS forwarder
- ▶ Configuring a standalone DHCP/DNS server
- ▶ Configuring dynamic DNS

Introduction

After installing pfSense and performing the initial configuration steps, we have the basic structure of our system in place. So far, we have:

- ▶ Determined our system requirements
- ▶ Set up SSH access
- ▶ Assigned our WAN, LAN, and optional (DMZ) interfaces

At this point, we're ready to begin configuring the essential networking services that our pfSense machine will provide.

- ▶ The DHCP service allows clients to obtain IP addresses automatically
- ▶ The DNS service translates IP addresses into readable DNS names, and vice-versa
- ▶ The Dynamic DNS service allows pfSense to automatically update the dynamic DNS record when your public IP address changes

Configuring the DHCP server


This recipe describes how to configure the DHCP service in pfSense. The DHCP service assigns an IP address to any client who requests one.

Getting ready

PfSense can only be configured as a DHCP server for interfaces configured with a static IP address. Using the examples in this book, that includes the LAN and DMZ interfaces but not the WAN. This example recipe will configure the DHCP server for your DMZ interface.

How to do it...

1. Browse to **Services | DHCP Server**.
2. Choose the **DMZ** tab.
3. Check **Enable DHCP server on DMZ interface**:



The screenshot shows the 'Services: DHCP server' configuration page in pfSense. The 'DMZ' tab is selected. The 'Enable DHCP server on DMZ interface' checkbox is checked. Below it, the 'Deny unknown clients' checkbox is unchecked, with a note: 'If this is checked, only the clients defined below will get DHCP leases from this server.'

4. Choose a **Range** of IP addresses for DHCP clients to use. This range must be contiguous and within the **Available range** listed above the **Range**:

Subnet	192.168.2.0
Subnet mask	255.255.255.0
Available range	192.168.2.1 - 192.168.2.254
Range	<input type="text" value="192.168.2.50"/> to <input type="text" value="192.168.2.99"/>

5. **Save** the changes and the DHCP service will be started.
6. **Apply** the changes, if necessary.

How it works...

A DHCP server accepts requests from clients and assigns them an available IP address.

There's more...

A DHCP server fulfills a client request by handing out the first available IP address. This means that it's very likely that a client will receive a different IP address with every request.

In order to ensure that a client always receives the same IP address, we can create static DHCP mapping. See the next recipe, *Creating static DHCP mappings*, for more information.

Deny Unknown Clients

Enabling this option ensures that only clients with static DHCP mappings will receive an IP address. DHCP requests from all other clients will be ignored.

This is different from **Enable static ARP entries** where unknown clients **will** receive an IP address, although they won't be able to communicate with the firewall (on that interface) in anyway.

DNS Servers

Specify any DNS server to be automatically assigned to our DHCP clients. If left blank, pfSense will automatically assign DNS servers to our clients in one of the following two ways:

- ▶ If DNS Forwarder is enabled, then the IP address of the interface is used. This is because the DNS Forwarder turns the pfSense machine itself into a DNS server, so the IP of the pfSense machine (that is, the gateway, which varies by interface) is assigned to each client.
- ▶ If DNS Forwarder isn't enabled, then the DNS Servers configured on the **General Setup** page are used. And of course if, **Allow DNS server list to be overridden by DHCP/PPP on WAN** is enabled in **General Setup**, then the DNS servers obtained through the WAN will be used instead.

Gateway

The interface gateway will be provided to clients by default (that is, the static IP of the interface), but can be overridden here if necessary.

Domain Name

The domain name specified in **General Setup** is used by default, but an alternative can be specified here.

Default Lease Time

An alternative lease time can be specified here for clients who do not request a specific expiration time. The default is 7200 seconds.

Maximum Lease Time

An alternative maximum lease time can be specified for clients that ask for a specific expiration time. The default is 86400 seconds.

Failover Peer IP

CARP-configured systems can specify a fail-over IP address here. See CARP configuration in the *Configuring CARP firewall failover* recipe in *Chapter 6, Redundancy, Load Balancing, and Failover* for more information.

Static ARP

Enabling static ARP entries will only allow clients with DHCP mappings to communicate with the firewall on this interface. Unknown clients will still receive an IP address, but all communication to the firewall will be blocked.

This is different from **Deny Unknown Clients** where unknown clients won't even receive an IP address.

Dynamic DNS

Enable clients to automatically register with the **Dynamic DNS** domain specified.

Additional BOOTP/DHCP Options

Enter any custom DHCP option here. Visit <http://www.iana.org/assignments/bootp-dhcp-parameters/bootp-dhcp-parameters.xml> for a list of options.

See also

- ▶ The *Creating static DHCP mappings* recipe
- ▶ The *Configuring CARP firewall failover* recipe in *Chapter 6, Redundancy, Load Balancing, and Failover*

Creating static DHCP mappings


This recipe describes how to add static DHCP mappings in pfSense. A static DHCP mapping ensures a client is always given the same IP address.







Getting ready

Creating static DHCP mappings is only applicable for interfaces using the DHCP service.

How to do it...




1. Browse to **Status | DHCP Leases** to view the list of clients who have issued DHCP requests.

Status: DHCP leases 





IP address	MAC address	Hostname	Start	End	Online	Lease Type	
192.168.1.50	00:1e:37:8a:cc:43	thinkpad	2011/01/16 11:55:24	2011/01/16 13:55:24	online	active	  
192.168.2.50	00:22:43:64:22:f3	asus1000he	2011/01/16 11:28:20	2011/01/16 13:28:20	offline	active	  

[Show all configured leases](#)

2. Click the “plus” button to add a new static DHCP mapping.
3. The MAC address will be pre-filled.
4. Enter an **IP address**, which must be outside the range of dynamically assigned DHCP addresses.
5. The **Hostname** may be pre-filled. If not, enter one.
6. Enter a **Description**.




Services: DHCP: Edit static mapping   

Static DHCP Mapping

MAC address	 00:1e:37:8a:cc:43 Copy my MAC address <small>Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx</small>
IP address	 192.168.1.100 <small>If no IP address is given, one will be dynamically allocated from the pool.</small>
Hostname	 thinkpad <small>Name of the host, without domain part.</small>
Description	 Lenovo Thinkpad T61p <small>You may enter a description here for your reference (not parsed).</small>

[Save](#) [Cancel](#)

7. **Save** the changes.
8. **Apply** changes, if necessary. Scroll to the bottom of the **DHCP Server** page and verify that your new mapping exists.

MAC address	IP address	Hostname	Description	  
00:1e:37:8a:cc:43	192.168.1.100	thinkpad	Lenovo Thinkpad T61p	




How it works...

When a client connects to our DHCP server, the firewall first checks for a mapping. If the client's MAC address matches a mapping we've specified, then the DHCP server uses the IP address specified in the mapping. If no mapping exists for our client's MAC address, our DHCP server uses an IP address from its available range.

There's more...

Static mappings can be viewed at the bottom of the DHCP Server configuration page for each interface by browsing to the **Services** | **DHCP Server** | **Interface** tab.

All static mappings for a given interface can be managed here. Existing mappings can be modified or removed, and new static mappings can be created, but you'll have to enter the MAC address manually.

MAC address	IP address	Hostname	Description	  
00:1e:37:8a:cc:43	192.168.1.100	thinkpad	Lenovo Thinkpad T61p	

See also

- ▶ *The Configuring the DHCP server recipe*
- ▶ *The Configuring the DHCP relay recipe*

Configuring the DHCP relay

This recipe describes how to configure pfSense to relay DHCP requests between broadcast domains. Specifying a DHCP relay is an alternative to configuring the DHCP service on pfSense itself.

Getting ready

DHCP Relay can only be enabled if the DHCP server is disabled on all interfaces. If necessary, first disable the DHCP service on all interfaces as follows:

1. Browse to the **Services | DHCP Server | Interface** tab (for example, LAN).
2. Uncheck **Enable DHCP Server on LAN Interface**.
3. **Save** the changes.
4. **Apply** changes, if necessary.

LAN DMZ

☐ Enable DHCP server on LAN interface

☒ Deny unknown clients
If this is checked, only the clients defined below will get DHCP leases from this server.

Subnet	192.168.1.0
Subnet mask	255.255.255.0
Available range	192.168.1.1 - 192.168.1.254
Range	<input type="text" value="192.168.1.100"/> to <input type="text" value="192.168.1.199"/>

How to do it...

1. Browse to **Services | DHCP Relay**.
2. Check **Enable DHCP Relay on Interface**.
3. Select the interfaces on which the relay will be applied. Use *Ctrl* + click to select multiple interfaces.
4. Enter the IP address of the existing DHCP Servers to be used as the **Destination server**. Multiple IP addresses may be entered, separated by commas.
5. **Save** the changes.

6. **Apply** changes, if necessary.

Services: DHCP Relay

DHCP Relay configuration

Enable ☒ **Enable DHCP relay on interface**

Interface(s)

LAN DMZ

Interfaces without an ip address will not be shown.

☐ **Append circuit ID and agent ID to requests**
If this is checked, the DHCP relay will append the circuit ID (pfSense interface number) and the agent ID to the DHCP request.

Destination server

192.168.1.22

This is the IP address of the server to which the DHCP packet is relayed. You can enter multiple ip address server entries separated by commas. Select "Proxy requests to DHCP server on WAN subnet" to relay DHCP packets to the server that was used on the WAN interface.

Save

How it works...

PfSense can be configured to relay DHCP requests to existing DHCP servers. Any incoming DHCP request will be forwarded to the server(s) specified and the response will be returned to the client.

Append Circuit ID and Agent ID to Requests

PfSense can append its interface number (circuit ID) and agent ID to DHCP requests, if checked.

Relay requests to the WAN DHCP server

Select this option to relay all requests to the DHCP defined in your WAN connection.

At the time of writing this book, this feature hadn't yet been implemented in the pfSense 2.0 Beta version.

See also

- ▶ The *Configuring the DHCP server* recipe
- ▶ The *Creating static DHCP mappings* recipe

Specifying alternate DNS servers

This recipe describes how to configure pfSense to use DNS servers other than those provided by your WAN connection.

Getting ready

When it comes to resolving DNS names, most environments will rely on the DNS servers provided by their ISP through their WAN connection. By default, no DNS servers are defined in pfSense and the **Allow DNS server list to be overridden by DHCP/PPP on WAN** is checked. However, to manually specify alternate DNS servers follow the instructions in the next subsection.

How to do it...

1. Browse to **System | General Setup**.
2. The **DNS servers** section contains the following settings:
 - Specify the IP address and gateway for each of the existing **DNS servers**.
 - Uncheck **Allow DNS server list to be overridden by DHCP/PPP on WAN**.
3. **Save** changes.
4. **Apply** changes, if necessary.

The screenshot shows the 'DNS servers' configuration page in pfSense. It features a table with two columns: 'DNS Server' and 'Use gateway'. There are four rows, each with a pencil icon for editing. The IP addresses are 4.2.2.1, 4.2.2.2, 4.2.2.3, and 4.2.2.4, and the gateway for all is 'WAN'. Below the table, there is explanatory text about IP addresses and a checkbox for 'Allow DNS server list to be overridden by DHCP/PPP on WAN' which is currently unchecked.

DNS Server	Use gateway
4.2.2.1	WAN ▼
4.2.2.2	WAN ▼
4.2.2.3	WAN ▼
4.2.2.4	WAN ▼

IP addresses: these are also used for the DHCP service, DNS forwarder and for PPTP VPN clients.

In addition, select the gateway for each DNS server. You should have a unique DNS server per gateway.

☐ **Allow DNS server list to be overridden by DHCP/PPP on WAN**
If this option is set, pfSense will use DNS servers assigned by a DHCP/PPP server on WAN for its own purposes (including the DNS forwarder). However, they will not be assigned to DHCP and PPTP VPN clients.

How it works...

The DNS servers specified here are the system defaults and will always take priority unless specifically overridden by the following options.



The DNS servers listed here (4.2.2.1 – 4.2.2.4) are public DNS servers that are often very helpful when trying to troubleshoot and diagnose DNS issues.

Using the DNS Forwarder

If the DNS Forwarder is enabled, we can override the DNS servers for individual domains or even override results for individual devices. For more information, see the following *Configuring the DNS Forwarder* recipe. The DNS Forwarder takes precedence over all DNS requests.

Using your WAN DNS servers

When **Allow DNS server list to be overridden by DHCP/PPP on WAN** is enabled, pfSense will attempt to resolve DNS names using the DNS servers provided by the WAN before failing over to the servers defined in this list. After the DNS Forwarder, this option takes precedence over DNS requests.

See also

- ▶ The *Configuring the DNS Forwarder* recipe

Configuring the DNS Forwarder


This recipe describes how to configure the DNS Forwarder in pfSense. The DNS Forwarder allows pfSense to act as a DNS server with a variety of features.

Getting ready

The DNS Forwarder allows pfSense to resolve DNS requests using hostnames obtained by the DHCP service, static DHCP mappings, or manually entered information. The DNS Forwarder can also forward all DNS requests for a particular domain to a server specified manually.

How to do it...

1. Browse to **Services | DNS Forwarder | Enable DNS Forwarder**.
2. If **Register DHCP leases in DNS Forwarder** is enabled, any devices in **Status | DHCP Leases** will be served if a match is found.
3. If **Register DHCP static mappings in DNS Forwarder** is enabled, any devices mapped on any interface tab in **Services | DHCP Server** will be served if a match is found.

Services: DNS forwarder 

☒ **Enable DNS forwarder**

☐ **Register DHCP leases in DNS forwarder**
If this option is set, then machines that specify their hostname when requesting a DHCP lease will be registered in the DNS forwarder, so that their name can be resolved. You should also set the domain in **System: General setup** to the proper value.

☒ **Register DHCP static mappings in DNS forwarder**
If this option is set, then DHCP static mappings will be registered in the DNS forwarder, so that their name can be resolved. You should also set the domain in **System: General setup** to the proper value.

4. Specify individual **Hosts** to be served as DNS records by clicking the “plus” button to add a record. Devices in this list are checked first; so even if a record exists elsewhere, the record here takes precedence and is immediately returned.

- Specify a DNS server for a particular **Domain** by clicking the “plus” button to add a record. These records are checked immediately after the individual records are defined above; so, a match here will take precedence over records that may exist elsewhere.

Note:
If the DNS forwarder is enabled, the DHCP service (if enabled) will automatically serve the LAN IP address as a DNS server to DHCP clients so they will use the forwarder. The DNS forwarder will use the DNS servers entered in System: General setup or those obtained via DHCP or PPP on WAN if the "Allow DNS server list to be overridden by DHCP/PPP on WAN" is checked. If you don't use that option (or if you use a static IP address on WAN), you must manually specify at least one DNS server on the System:General setup page.

You may enter records that override the results from the forwarders below.

Host	Domain	IP	Description
wrt54gl	example.com	192.168.1.2	My wireless access point defines its own IP (i.e. it doesn't use DHCP) so when entered here it will be resolved by pfSense.

Below you can override an entire domain by specifying an authoritative DNS server to be queried for that domain.

Domain	IP	Description
google.com	192.168.1.222	This will direct any DNS requests for google.com to an internal IP. This is just an example, I wouldn't recommend doing this.

- Save** the changes.
- Apply** changes, if necessary.

How it works...

If enabled, the DNS Forwarder takes priority over all DNS requests and responds to them in the following order:

- Individual device records (**Services | DNS Forwarder**).
- Domain specific records (**Services | DNS Forwarder**).
- DHCP static mappings (**Services | DHCP Server | Interface** tab).
- DHCP leases (**Status | DHCP Leases**).

See also

- ▶ The *Configuring the DHCP server* recipe
- ▶ The *Creating static DHCP mappings* recipe
- ▶ The *Configuring a standalone DHCP/DNS server* recipe

Configuring a standalone DHCP/DNS server

This recipe describes how to configure pfSense as a standalone DHCP and DNS server.

How to do it...

1. Configure pfSense as a DHCP Server. See the *Configuring the DHCP server* recipe for details.
2. Create DHCP mappings for every device in the system that will obtain its IP address automatically through DHCP. See the *Creating static DHCP mappings* recipe for details.
3. Browse to **System | General Setup**.
4. Ensure that no other DNS servers are specified.
5. Enable **Allow DNS server list to be overridden by DHCP/PPP on WAN**, so that pfSense can resolve external addresses using the DNS servers provided by your ISP through your WAN connection.
6. **Save** the changes.

7. **Apply** changes, if necessary.

System: General Setup

System

Hostname

pfsense

Name of the firewall host, without domain part
 e.g. firewall

Domain

example.com

Do not use 'local' as a domain name. It will cause local hosts running mDNS (avahi, Bonjour, etc.) to be unable to resolve local hosts not running mDNS.
 e.g. mycorp.com, home, office, private, etc.

DNS servers

DNS Server	Use gateway
	None ▼
	None ▼
	None ▼
	None ▼

IP addresses: these are also used for the DHCP service, DNS forwarder and for PPTP VPN clients.

 In addition, select the gateway for each DNS server. You should have a unique DNS server per gateway.

☒ **Allow DNS server list to be overridden by DHCP/PPP on WAN**
 If this option is set, pfSense will use DNS servers assigned by a DHCP/PPP server on WAN for its own purposes (including the DNS forwarder). However, they will not be assigned to DHCP and PPTP VPN clients.

8. Browse to **System | DNS Forwarder**.
9. Check **Enable DNS Forwarder**.
10. Check **Register DHCP static mappings in DNS forwarder**.

Services: DNS forwarder

☒ **Enable DNS forwarder**

☐ **Register DHCP leases in DNS forwarder**
 If this option is set, then machines that specify their hostname when requesting a DHCP lease will be registered in the DNS forwarder, so that their name can be resolved. You should also set the domain in System: General setup to the proper value.

☒ **Register DHCP static mappings in DNS forwarder**
 If this option is set, then DHCP static mappings will be registered in the DNS forwarder, so that their name can be resolved. You should also set the domain in System: General setup to the proper value.

Note:

If the DNS forwarder is enabled, the DHCP service (if enabled) will automatically serve the LAN IP address as a DNS server to DHCP clients so they will use the forwarder. The DNS forwarder will use the DNS servers entered in System: General setup or those obtained via DHCP or PPP on WAN if the "Allow DNS server list to be overridden by DHCP/PPP on WAN" is checked. If you don't use that option (or if you use a static IP address on WAN), you must manually specify at least one DNS server on the System:General setup page.

40

11. Create a **Host** record for any device that needs to be resolved but doesn't have a DHCP mapping (that is, devices that define their own IP).
12. Create a **Domain** record for any DNS requests you'd like to redirect for a particular domain.

Host	Domain	IP	Description
wrt54gl	example.com	192.168.1.2	Linksys WRT54GL Wireless Access Point

Below you can override an entire domain by specifying an authoritative DNS server to be queried for that domain.

Domain	IP	Description
--------	----	-------------

13. **Save** the changes.
14. **Apply** changes, if necessary.

How it works...

If the DNS Forwarder is enabled, every DNS request from every interface will be processed by pfSense. Individual host records are checked first, and if a match is found, the associated IP address is immediately returned.

By enabling the **Register DHCP Static Mappings** option, you won't have to worry about creating DNS records for those devices. This is my preferred method of using pfSense as a DNS server. As long as we create a static mapping for every device on our network, their hostnames will resolve automatically.

Using this method, we'll only have to add explicit hostname records for devices that specify their own IP address (that is, devices that don't use DHCP), which should be few and far between.

Register DHCP Leases in DNS Forwarder

If the **Register DHCP Leases in DNS Forwarder** option is enabled, pfSense will automatically register any devices that specify a hostname when submitting a DNS request. The downside, of course, is that not all devices submit a hostname and even when they do, it is sometimes cryptic. I prefer to only register important devices using DHCP static mappings, and all other (unimportant/unknown) devices can be referenced using their IP addresses.

See also

- ▶ The *Configuring the DHCP server* recipe
- ▶ The *Creating static DHCP mappings* recipe
- ▶ The *Configuring the DNS Forwarder* recipe

Configuring dynamic DNS

This recipe describes how to configure a dynamic DNS service in pfSense.

Getting ready

PfSense's integrated dynamic DNS service allows you to automatically update your dynamic DNS records when a change in an interface's IP address is detected.

How to do it...

1. Browse to **Services | Dynamic DNS**.
2. Click the **DynDNS** tab.
3. Click the "plus" button to add a new record.
4. Choose a **Service type** (that is, dynamic DNS service provider).
5. Specify an **Interface to monitor** (this is typically the WAN interface).
6. Specify our **Hostname** (that is, the friendly DNS name our dynamic DNS provider has supplied us with).
7. Toggle **Wildcards**, if applicable.
8. Enter your **username** and **password** you'd setup with our dynamic DNS provider.
9. Enter a friendly **description**.
10. **Save** changes.
11. **Apply** changes, if necessary.

Services: Dynamic DNS client

Dynamic DNS client

Disable

☐

Service type

DynDNS (dynamic) ▾

Interface to monitor

WAN ▾

Hostname

example.dyndns.org

Note:

Enter the complete host/domain name. example: myhost.dyndns.org

MX

Note:

With DynDNS service you can only use a hostname, not an IP address. Set this option only if you need a special MX record. Not all services support this.

Wildcards

☒ Enable Wildcard

Username

john doe

Username is required for all types except Namecheap and FreeDNS.

Password

••••••••

Description

Example DynDNS account information.

Save

Cancel

Note:

You must configure a DNS server in System: General setup or allow the DNS server list to be overridden by DHCP/PPP on WAN for dynamic DNS updates to work.

How it works...

Whenever the IP address of our interface changes, pfSense automatically connects to our dynamic DNS service and updates the IP address accordingly.

Pre-configured service types (dynamic DNS providers)

PfSense comes with the following popular dynamic DNS services pre-configured:

- ▶ DNS-O-Matic
- ▶ DynDNS (dynamic, static, custom)
- ▶ DHS
- ▶ DyNS
- ▶ easyDNS
- ▶ No-IP
- ▶ ODS
- ▶ ZoneEdit
- ▶ Loopia

- ▶ freeDNS
- ▶ DNSexit
- ▶ OpenDNS
- ▶ NameCheap

Specifying an alternative service using RFC 2136

We may specify a dynamic DNS service that doesn't come pre-configured as long as it adheres to the RFC 2136 standard. Choose the **Services | Dynamic DNS | RFC 2136** tab, and then fill in the appropriate fields using the information provided by our RFC 2136 compliant dynamic DNS service:

Services: RFC 2136 client: Edit

RFC 2136 client	
Enable	<input checked="" type="checkbox"/>
Interface to monitor	WAN
Hostname	example.dyndns.org
TTL	3600 seconds
Key name	keyname <small>This must match the setting on the DNS server.</small>
Key type	<input type="radio"/> Zone <input type="radio"/> Host <input checked="" type="radio"/> User
Key	paste key here <small>Paste an HMAC-MD5 key here.</small>
Server	server
Protocol	<input type="checkbox"/> Use TCP Instead of UDP
Description	Standards compliant Dyn-DNS example connection.

Save
Cancel

Note:
You must configure a DNS server in System: General setup or allow the DNS server list to be overridden by DHCP/PPP on WAN for dynamic DNS updates to work.

For more information, refer to:

Wikipedia – DynamicDNS

http://en.wikipedia.org/wiki/Dynamic_DNS

RFC 2136 Standard Documentation

<http://tools.ietf.org/html/rfc2136>

3

General Configuration

In this chapter, we will cover:

- ▶ Creating an alias
- ▶ Creating a NAT port forward rule
- ▶ Creating a firewall rule
- ▶ Creating a schedule
- ▶ Remote desktop access, a complete example

Introduction

The core functionality of any firewall involves creating port forward and firewall security rules, and pfSense is no different. These core features, plus others, can all be found on the main **Firewall** menu of the pfSense web interface.

This chapter explains how to configure these rules and the features associated with them. Once you've done a few, you'll realize just how easy it is with pfSense.

Creating an alias

This recipe describes how to use, create, edit, and delete aliases. Aliases provide a degree of separation between our rules and values that may change in the future (for example, IP addresses, ports, and so on). It's best to use aliases whenever possible.

How to do it...

1. Browse to **Firewall | Aliases**.
2. Click the "plus" button to add a new alias.
3. Add a **Name** for the alias.
4. Add an optional **Description**.
5. Select an alias **Type** and finish the configuration based on that selection.

See the following *There's more* section for details on each alias type (Hosts, Networks, Ports, OpenVPN Users, URL, and URL Table).

Firewall: Aliases: Edit

Alias Edit

Name
The name of the alias may only consist of the characters "a-z, A-Z and 0-9".

Description
You may enter a description here for your reference (not parsed).

Type

Host(s)

Enter as many hosts as you would like. Hosts must be specified by their IP address.

IP	Description
192.168.1.200	The IP address of Computer1.

6. **Save** the changes.
7. **Apply changes**, if necessary.

How it works...

An **alias** is a place-holder (that is a variable) for information that may change. A **host alias** is a good example; we can create a host alias called **Computer1** and have it store an IP address of 192.168.1.200.

We can then create firewall and NAT rules that use the **Computer1** alias instead of explicitly specifying the IP address of Computer1, which may change. If the IP address of Computer1 does change, then we simply edit the alias instead of modifying numerous rules.

Aliases allow for the flexibility and simplification of future changes. It's best to use aliases whenever possible.

There's more...

Adding aliases *within* aliases is a great way to manage and simplify rules. To illustrate the power of aliases, let's say our organization has a single VoIP phone that must be allowed to communicate with our VoIP server.

An example of this rule without aliases is as follows:

	ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description	
<input type="checkbox"/>		TCP	192.168.1.111	*	192.168.1.200	5061	*	none		Allow Phone1 to our VoIP Server on our custom port	

A better example, using aliases is as follows:

	ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description	
<input type="checkbox"/>		TCP	voip_phone1	*	voip_server	voip_server_port	*	none		Allow Phone1 to our VoIP Server on our custom port	

An even better example, using sub-aliases is:

	ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description	
<input type="checkbox"/>		TCP	voip_all_phones	*	voip_server	voip_server_port	*	none		Allow all phones to our VoIP Server on our port	

Sub-aliases will allow us to easily add more phones by simply modifying an alias:

Firewall: Aliases: Edit

Alias Edit

Name
The name of the alias may only consist of the characters "a-z, A-Z and 0-9".

Description
You may enter a description here for your reference (not parsed).

Type

Host(s)

Enter as many hosts as you would like. Hosts must be specified by their IP address.

IP	voip_phone1	32	Description
	voip_phone2	32	
	voip_phone3	32	

Host alias

Selecting **Host(s)** as an alias **Type** allows you to create an alias that holds one or more IP addresses:

The screenshot shows the 'Host(s)' configuration window. At the top, the 'Type' dropdown is set to 'Host(s)'. Below it, a text box contains the instruction: 'Enter as many hosts as you would like. Hosts must be specified by their IP address.' The main table has two columns: 'IP' and 'Description'. The first row shows the IP '192.168.1.200' and the description 'The IP address of Computer1.'.

IP	Description
192.168.1.200	The IP address of Computer1.

Network alias

Selecting **Network(s)** as an alias **Type** allows you to create an alias that holds one or more networks (that is ranges of IP addresses):

The screenshot shows the 'Network(s)' configuration window. The 'Type' dropdown is set to 'Network(s)'. A text box explains: 'Networks are specified in CIDR format. Select the CIDR mask that pertains to each entry. /32 specifies a single host, /24 specifies 255.255.255.0, etc. Hostnames (FQDNs) may also be specified, using a /32 mask. You may also enter an IP range such as 192.168.1.1-192.168.1.254 and a list of CIDR networks will be derived to fill the range.' The table has columns for 'Network', 'CIDR', and 'Description'. Three entries are shown: '192.168.0.0' with CIDR '16', '192.168.0.0-192.168.255.255' with CIDR '32', and 'www.bunkerhollow.com' with CIDR '32'.

Network	CIDR	Description
192.168.0.0	16	CIDR format of a typical private network.
192.168.0.0-192.168.255.255	32	Range format of a typical private network.
www.bunkerhollow.com	32	An example of a FQDN hostname.

Port alias

Selecting **Port(s)** as an alias **Type** allows you to create an alias that holds one or more ports:

The screenshot shows the 'Port(s)' configuration window. The 'Type' dropdown is set to 'Port(s)'. A text box states: 'Enter as many ports as you wish. Port ranges can be expressed by seperating with a colon.' The table has columns for 'Port' and 'Description'. Two entries are shown: '12345' and '55100:55199', both with a CIDR of '32'.

Port	Description
12345	An individual port.
55100:55199	A range of ports.

OpenVPN Users alias

Selecting **OpenVPN Users** as an alias **Type** allows you to create an alias that holds one or more OpenVPN usernames:

URL alias

Selecting **URL** as an alias **Type** allows you to create an alias that holds one or more URLs:

URL Table alias

Selecting **URL Table** as an alias **Type** allows you to create an alias that holds a single URL pointing to a large list of addresses. This can be especially helpful when you need to import a large list of IPs and/or subnets.

Using an alias

Aliases can be used anywhere you see a **red textbox**. Simply begin typing and pfSense will display any available aliases that match the text you've entered:



Alias auto-complete is context aware. For example, if the textbox requires a port number then pfSense will only display port alias matches.

Editing an alias

To modify an existing alias, follow these steps:

1. Browse to **Firewall | Aliases**.
2. Click the edit button to edit an alias.
3. Make the necessary changes.
4. **Save** the changes.
5. **Apply** the changes.

Deleting an alias:

To remove an existing alias, follow these steps:

1. Browse to **Firewall | Aliases**.
2. Click the delete button to delete an alias.
3. **Save** the changes.
4. **Apply** the changes.

Bulk-importing aliases

To import a list of multiple IP addresses, follow these steps:

1. Browse to **Firewall | Aliases**.
2. Click the import button to bulk import aliases.
3. Provide an **Alias Name**.
4. Provide an optional **Description**.
5. Paste a list of IP addresses, one per line, in the **Aliases to Import** textbox:

Firewall: Aliases: Bulk Import

Alias Import	
Alias Name	<input type="text" value="TimeWasters"/> <small>The name of the alias may only consist of the characters "a-z, A-Z and 0-9".</small>
Description	<input type="text" value="Websites I spend too much time on!"/> <small>You may enter a description here for your reference (not parsed).</small>
Aliases to Import	<input type="text" value="66.35.250.150"/> <input type="text" value="66.28.209.219"/> <input type="text" value="72.247.147.48"/> <small>Paste in the aliases to import separated by a carriage return. Common examples are lists of IPs, networks, blacklists, etc. The list may contain only IP addresses.</small>
<input type="button" value="Save"/> <input type="button" value="Cancel"/>	

6. **Save** the changes.
7. **Apply** the changes.

See also

- ▶ The *Creating a NAT port forward rule* recipe
- ▶ The *Creating a firewall rule* recipe
- ▶ Official Documentation at <http://doc.pfsense.org/index.php/Aliases>

Creating a NAT port forward rule

This recipe describes how to create, edit, and delete port forward rules.

Getting ready

The complexity of port forward rules can vary greatly. Every aspect of a port forward rule is detailed in the following *There's More* section so for the sake of simplicity. The following is an example of a typical port forward scenario. We will create a port forward rule to forward any incoming web requests (HTTP) to a computer we've configured as a web server.

How to do it...

1. Browse to **Firewall | NAT**.
2. Select the **Port Forward** tab.
3. Click the "plus" button to create a new NAT port forward rule.
4. For **Destination port range**, choose **HTTP** for the **from** and **to** drop-down boxes.
5. For **Redirect target IP** specify the web server this traffic will be forwarded to, by alias or IP address.
6. For **Redirect target Port** choose **HTTP**.
7. Add a **Description**, such as **Forward HTTP to webserver1**.
8. **Save** the changes.

9. **Apply** the changes.

Destination port range	from: HTTP to: HTTP Specify the port or port range for the destination of the packet for this mapping. Hint: you can leave the 'to' field empty if you only want to map a single port
Redirect target IP	webserver1 Enter the internal IP address of the server on which you want to map the ports. e.g. 192.168.1.12
Redirect target port	HTTP Specify the port on the machine with the IP address entered above. In case of a port range, specify the beginning port of the range (the end port will be calculated automatically). Hint: this is usually identical to the 'from' port above
Description	Forward HTTP to webserver1 You may enter a description here for your reference (not parsed).
No XMLRPC Sync	<input type="checkbox"/> HINT: This prevents the rule from automatically syncing to other CARP members.
NAT reflection	use system default
Filter rule association	Add associated filter rule



By default, a firewall rule is created to allow the forwarded traffic to pass, but it's vital to remember that NAT and firewall rules are distinct and separate. NAT rules forward traffic, while firewall rules block or allow traffic. Remember, just because a NAT rule is forwarding traffic doesn't necessarily mean the firewall rules will allow it

How it works...

All traffic passes through the list of NAT rules, with the following criteria:

- ▶ Interface
- ▶ Protocol
- ▶ Source and Source port range
- ▶ Destination and Destination port range

If any traffic matches all of this rule's criteria, that traffic will be redirected to the **Redirect target IP** and **Redirect target port** specified.



Like all rules in pfSense, NAT rules are evaluated from the top down. The first rule to match is executed immediately and the rest are skipped.

Our specific examples can be read as:

Traffic from:

- ▶ The Internet (**Interface:** WAN)
- ▶ From any client (**Source**) on any port (**Source Port Range**)

Traveling to:

- ▶ Our public IP address (**Destination** WAN address)
- ▶ With a website request (**Protocol:** TCP, **Destination Port Range:** HTTP)

Will be redirected to:

- ▶ A particular computer (**Redirect Target IP:** Webserver1)
- ▶ With the same request (**Protocol:** TCP, **Redirect Target Port:** HTTP).

There's more...

NAT rules can be configured using a variety of options, the details of each is as follows (bold items are generally the only ones which need to be modified):

- ▶ **Disabled:** Enable or disable a NAT rule by checking this box.
- ▶ **No RDR (NOT):** Enabling this option will disable traffic redirection.
- ▶ **Interface:** Specify the interface for this NAT rule (usually WAN).
- ▶ **Protocol:** Specify the protocol for this NAT rule. Typically TCP, UDP, or TCP/UDP is specified, but GRE and ESP exist as well.
- ▶ **Source:** Typically the source is left to the default value of **any**, but you can specify a specific source if needed.
- ▶ **Source Port Range:** Generally **Source Port Range** is left to the default value of **any**, but you can specify the ports if needed.
- ▶ **Destination:** Most often, the **Destination** is left to the default value of the WAN address (that is your public IP address), but an alternative can be chosen if necessary.
- ▶ **Destination Port Range:** This is the port the traffic will be requesting. If we're forwarding web traffic, we would select **HTTP**, which is so common that it's built into the drop-down list, but choosing (**other**) and specifying port 80 would work just the same. If specifying a custom port (let's say we want to forward torrent traffic on port 46635), remember to **use an alias!**

- ▶ **Redirect Target IP:** This is the IP address of the internal computer we will forward traffic to. Remember to **use an alias!**
- ▶ **Redirect Target Port:** This is the port of the computer specified previously that traffic will be forwarded to. Remember to **use an alias!**
- ▶ **Description:** The description provided here will be copied into any firewall rules (and preceded by the word "NAT") that are automatically generated.
- ▶ **No XMLRPC Sync:** Enable this option to prevent this rule from being applied to any redundant firewalls using CARP. Refer to the Configuring CARP Firewall Failover section in *Chapter 6, Redundancy, Load Balancing, and Failover* for more information.
- ▶ **NAT Reflection:** Using system default is almost always the case, but **NAT Reflection** can be enabled or disabled as per rule, if needed.
- ▶ **Filter Rule Association:** A firewall rule will automatically be created and associated to this NAT rule.

Port redirection

A true port forwarding rule will pass traffic to an internal machine on the *same* port that was requested (that is, the **Destination port range** and **Redirect target port** will match). However, there's nothing stopping you from redirecting to a different port if you'd like. There are two typical reasons for doing so:

- ▶ **Security Through Obscurity:** Everyone knows that the standard HTTP port is 80, but suppose you have a "secret" website which you don't want to be accessed easily. You can set the **Destination Port Range** to some obscure port (for example, 54321) and forward that to your internal web server's standard HTTP port 80. Users will have to know to browse to `http://www.example.com:54321` in order to access it.
- ▶ **Single Public IP Address:** Smaller environments with only a single public IP address may find themselves stuck if they want to expose a lot of public services. For example, "I want to remote into 2 different machines, but I only have 1 public IP address." With port redirection, we'll create two different NAT rules. The first will redirect port 50001 to Computer1 on MSRD (port 3389) and the second will redirect port 50002 to Computer2 on MSRD (port 3389). You can then remote into different machines using a single IP by specifying particular ports (for example, `example.com:50001`, `example.com:50002`, and so on).

See also

- ▶ The *Creating an alias* recipe
- ▶ The *Creating a firewall rule* recipe
- ▶ The *Configuring CARP firewall failover* recipe in *Chapter 6, Redundancy, Load Balancing, and Failover*

Creating a firewall rule

This recipe describes how to create a firewall rule.

Getting ready

As an example, we will create a firewall rule to allow the web traffic forwarded in by the NAT port forward rule we created in the previous recipe. If you've been following along, you'll know that the previous recipe automatically created the firewall rule we need, but instead we could have specified **None** for **Filter Rule Association** and used this recipe to create the rule ourselves.

How to do it...

1. Browse to **Firewall | Rules**.
2. Select the **WAN** tab.
3. Click the "plus" button to create a new firewall rule.
4. Specify the **WAN Interface**.
5. Specify the **TCP Protocol**.
6. Specify **any** as the **Source**.
7. Specify **any** as the **Source Port Range**.
8. Specify **Webserver1** as our **Destination**.
9. Specify **HTTP** as our **Destination Port Range**.
10. Specify a **Description**.
11. **Save** the changes.

12. Apply changes.

Firewall: Rules: Edit S I ?

Edit Firewall rule

Action	Pass ▼ Choose what to do with packets that match the criteria specified below. Hint: the difference between block and reject is that with reject, a packet (TCP RST or ICMP port unreachable for UDP) is returned to the sender, whereas with block the packet is dropped silently. In either case, the original packet is discarded.
Disabled	<input type="checkbox"/> Disable this rule Set this option to disable this rule without removing it from the list.
Interface	WAN ▼ Choose on which interface packets must come in to match this rule.
Protocol	TCP ▼ Choose which IP protocol this rule should match. Hint: in most cases, you should specify TCP here.
Source	<input type="checkbox"/> not Use this option to invert the sense of the match. Type: any ▼ Address: / 31
Source port range	from: any ▼ to: any ▼ Specify the source port or port range for this rule. This is usually random and almost never equal to the destination port range (and should usually be "any") . Hint: you can leave the 'to' field empty if you only want to filter a single port.
Destination	<input type="checkbox"/> not Use this option to invert the sense of the match. Type: Single host or alias ▼ Address: Webserver1 / 31
Destination port range	from: HTTP ▼ to: HTTP ▼ Specify the port or port range for the destination of the packet for this rule. Hint: you can leave the 'to' field empty if you only want to filter a single port.
Log	<input type="checkbox"/> Log packets that are handled by this rule Hint: the firewall has limited local log space. Don't turn on logging for everything. If you want to do a lot of logging, consider using a remote syslog server (see the Diagnostics: System logs: Settings page).
Description	Allow any to Webserver1 HTTP You may enter a description here for your reference.

Save Cancel

How it works...

All traffic passes through the list of firewall rules. If any traffic packet matches all of the rules' criteria, that rule will be executed (the packet will be allowed or denied).



Like all rules in pfSense, firewall rules are evaluated from the top down. The first rule to match is executed immediately and the rest are skipped. See the following *Ordering Firewall Rules* section for more information.

This rule can be read as: "Any port from any client on the Internet is allowed to access our web server's port 80".

There's more...

Firewall rules are highly configurable. Details of each firewall rule option are as follows:

- ▶ **Action:** The type of action defined will be enforced if the rule is matched.
 - ❑ **Pass:** If all the criteria match, the packet will be allowed to pass.
 - ❑ **Block:** If all the criteria matches, the packet will not be allowed to pass (some refer to this as a **silent drop**).
 - ❑ **Reject:** If all the criteria match, the packet will be returned to the sender.
- ▶ **Disabled:** Disable a rule without having to delete it entirely.
- ▶ **Interface:** Traffic originating from the specified interface will be subject to this rule. This is typically the WAN.
- ▶ **Protocol:** Specify the protocol to be matched; this varies depending on the type of traffic this rule defines.
- ▶ **Source:** This is typically **any** when referring to incoming traffic.
- ▶ **Source Port Range:** This is typically **any** when referring to incoming traffic.
- ▶ **Destination:** This is typically the alias or IP address of computer which is servicing this traffic.
- ▶ **Destination Port Range:** This is typically the specific port of the computer which is servicing this traffic.
- ▶ **Log:** Enable logging to record packets that match this rule.
- ▶ **Description:** Enter meaningful descriptions that will make it easier to understand the rule.

We rarely know the source port!

When specifying rules, it's important to remember that the **Source Port Range** is almost always set to **any**. People often make the mistake of specifying a **Source Port Range** when they shouldn't. Remember, when you request a website, you are requesting port 80 on someone else's computer and your computer decides what port to open on yours. This is your source port, an ever-changing port which you probably never know about. So 99 percent of the time, we won't know the **Source Port Range** of the traffic we are allowing in.

Ordering firewall rules

PfSense rules are always evaluated from the top down. The first rule to match is executed and the rest of the rules are skipped. Many administrators will include very specific rules at the top and more generic rules at the bottom. To reorder a rule, select the rule and then click the appropriate **move selected rules before this rule** button:

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description	
	*	RFC 1918 networks	*	*	*	*	*		Block private networks	
	*	Reserved/not assigned by IANA	*	*	*	*	*		Block bogus networks	
	TCP	*	*	Tigas	22 (SSH)	*	none		NAT Forward TigasSshPort to Tigas SSH	
	TCP	*	*	Webserver1	80 (HTTP)	*	none		Allow any to Webserver1 HTTP.	

move selected rules before this rule

Duplicating a firewall rule

Often, we may want to create a new rule that's very similar to an existing rule. To save time, we can create a new rule that's pre-filled with the same options as an existing rule by clicking the "plus" button:

	TCP	*	*	Webserver1	80 (HTTP)	*	none		Allow any to Webserver1 HTTP.	
	TCP	*	*	Tigas	22 (SSH)	*	none		NAT Forward TigasSshPort to Tigas SSH	

add a new rule based on this one

Advanced features

New to pfSense 2.0 is the firewall rule **Advanced Features** section. Each of the following features can be specified as criteria for a rule. If an advanced feature is specified, the rule will only be executed if a match is found. Click the **Advanced** button to display the following configuration settings for each feature:

- **Source OS:** This option will attempt to match the operating system of the source traffic:

Source OS

OS Type: Windows ▼
Note: this only works for TCP rules

- **Diffserv Code Point:** Diffserv is a mechanism for providing Quality of Service (QoS) of network traffic. Systems can prioritize traffic based on their code point values:

Diffserv Code Point

af11

- **Advanced Options:** Allows for the specification of advanced IP Options:

Advanced Options	<input type="checkbox"/>	This allows packets with IP options to pass. Otherwise they are blocked by default. This is usually only seen with multicast traffic.
	<input type="checkbox"/>	This will disable auto generated reply-to for this rule.
	<input type="text"/>	You can mark a packet matching this rule and use this mark to match on other NAT/filter rules. It is called Policy filtering
	<input type="text"/>	You can match packet on a mark placed before on another rule.
	<input type="text"/>	Maximum state entries this rule can create
	<input type="text"/>	Maximum number of unique source hosts
	<input type="text"/>	Maximum number of established connections per host
	<input type="text"/>	Maximum state entries per host
	<input type="text"/> / <input type="text"/>	Maximum new connections / per second(s)
	<input type="text"/>	State Timeout in seconds
	NOTE: Leave fields blank to disable that feature.	

- **TCP Flags:** Specific TCP flags may be set here:

TCP flags		FIN	SYN	RST	PSH	ACK	URG
	set	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
	out of	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
	<input type="checkbox"/> Any flags.						

Use this to choose TCP flags that must be set or cleared for this rule to match.

- **State Type:** Specify a particular state tracking mechanism:

State Type	keep state ▼	
	HINT: Select which type of state tracking mechanism you would like to use. If in doubt, use keep state.	
	keep state	Works with all IP protocols.
	sloppy state	Works with all IP protocols.
	synproxy state	Proxies incoming TCP connections to help protect servers from spoofed TCP SYN floods. This option includes the functionality of keep state and modulate state combined.
none	Do not use state mechanisms to keep track. This is only useful if you're doing advanced queueing in certain situations. Please check the documentation.	

- **No XMLRPC Sync:** Prevent a rule from syncing with the other CARP members:

No XMLRPC Sync	<input type="checkbox"/>	
HINT: This prevents the rule from automatically syncing to other CARP members.		

- **Schedule:** Specify the schedule for when this rule is valid. Schedules defined in **Firewall | Schedules** will appear here:

Schedule	WorkHours ▼	
Leave as 'none' to leave the rule enabled all the time.		

- **Gateway:** Gateways other than the default may be specified here:

Gateway	default ▼	
Leave as 'default' to use the system routing table. Or choose a gateway to utilize policy based routing.		

- **In/Out:** Specify alternative queues and virtual interfaces:

In/Out	none ▼ / none ▼	
Choose the Out queue/Virtual interface only if you have selected In too. The Out selection is applied to traffic going out the interface the rule is created, In is the incoming one.		
If you are creating a rule on the Floating tab if the direction is In then the same rules apply, if the direction is out the selections are reverted Out is for incoming and In is for outgoing and if you do not select any direction use only the In since the Out selection does not make sense in there to prevent oddities.		

- **Ackqueue/Queue:** Specify alternative acknowledge queues:

Ackqueue/Queue	<div>none ▾ / none ▾</div>
Choose the Acknowledge Queue only if you have selected Queue.	

- ▶ **Layer7:** Specify an alternative **Layer7** container:

Layer7	<div>none ▾</div>
Choose a Layer7 container to apply application protocol inspection rules. These are valid for TCP and UDP protocols only.	

See also

- ▶ The *Creating an alias* recipe
- ▶ The *Creating a NAT port forward rule* recipe
- ▶ The *Creating a schedule* recipe

Creating a schedule

This recipe describes how to create a schedule.

Getting ready

Schedules allow us to specify *when* rules are enabled. They are primarily used with firewall rules, but their generic design allows them to be used with other existing and future pfSense features. If a firewall rule specifies a schedule, the rule is only enabled during that time period. In the following example, we'll define a schedule for our normal 9am-5pm work hours.



When creating schedules, it's essential to have your NTP time-sync settings properly configured against a reliable server. Also be aware of time-zone differences and day-light savings time.

How to do it...

1. Browse to **Firewall | Schedules**.
2. Click the "plus" button to create a new schedule.
3. Enter a **Schedule Name**, such as **WorkHours**.
4. Enter a **Description**, such as **Regular work week hours**.
5. In the **Month** section, click **Mon**, **Tue**, **Wed**, **Thu**, and **Fri** to select all the days of the work week.

6. Specify a 9 am as the **Start Time** and 5 pm as the **Stop Time**.
7. Enter a **Time Range Description**, such as **Monday-Friday 9am-5pm**.
8. Click **Add Time**.

Firewall: Schedules: Edit

Schedule information

Schedule Name

The name of the alias may only consist of the characters a-z, A-Z and 0-9

Description

You may enter a description here for your reference (not parsed).

Month

March 00 ▾

March 2000

Mon	Tue	Wed	Thu	Fri	Sat	Sun
		1	2	3	4	5
6	7	8	9	10	11	12
13	14	15	16	17	18	19
20	21	22	23	24	25	26
27	28	29	30	31		

Click individual date to select that date only. Click the appropriate weekday Header to select all occurrences of that weekday.

Time

Start Time

Stop Time

9 ▾ Hr 00 ▾ Min 17 ▾ Hr 00 ▾ Min

Select the time range for the day(s) selected on the Month(s) above. A full day is 0:00-23:59.

Time Range Description

You may enter a description here for your reference (not parsed).

Add Time Clear Selection

9. Note that the repeating time is added to **Configured Ranges**:

Schedule repeat

Configured Ranges

Day(s)	Start Time	Stop Time	Description
Mon - Fri	9:00	17:00	Monday-Friday 9am-5pm

Save Cancel

10. **Save** the changes.
11. **Apply** the changes, if necessary.

How it works...

Features associated with a schedule will only be valid during the schedule specified. To associate a firewall rule with the schedule we've just created:

1. Edit an existing firewall rule, or create a new one.
2. Click the **Schedule Advanced** button to show the scheduling options.
3. Choose **WorkHours** as our **Schedule**:



Schedule

WorkHours ▼


Leave as 'none' to leave the rule enabled all the time.

4. Save the changes.
5. Apply the changes.



There's more...

Icons exist throughout the system to help determine at a glance if a schedule is active or not:

- **Firewall | Schedules:** Active schedules show a "clock" icon:



Firewall: Schedules

Name	Time Range(s)	Description
AwakeHours 	Mon - Sun 6:00-20:00 Everyday 6am-10pm	Hours I am awake.
Weekend 	Sat - Sun 0:00-23:59 Entire weekend.	Weekend hours.
WorkHours	Mon - Fri 9:00-17:00 Weekdays 9am-5pm	Hours I am working.

Note:
Schedules act as placeholders for time ranges to be used in Firewall Rules.

- **Firewall | Rules:** Rules with active schedules (meaning the rules which are enabled) show a "green arrow" in the schedule column.

Rules with inactive schedules (meaning the rules which are disabled) show a "red x" in the schedule column:

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description
	*	RFC 1918 networks	*	*	*	*	*		Block private networks
	*	Reserved/not assigned by IANA	*	*	*	*	*	*	Block bogon networks
	TCP	*	*	Webserver1	80 (HTTP)	*	none	WorkHours	Allow any to Webserver1 HTTP during work hours.
	TCP	*	*	Webserver1	80 (HTTP)	*	none	Weekend	Allow any to Webserver1 HTTP on the weekend.

Selecting days or days of the week

The **Month** section works in two ways:

- **Selecting specific days:** Switch to the correct month and click the specific day (the year is irrelevant; any days selected will repeat every year):

Month


January 11 ▾

January 2011

Mon	Tue	Wed	Thu	Fri	Sat	Sun
					1	2
3	4	5	6	7	8	9
10	11	12	13	14	15	16
17	18	19	20	21	22	23
24	25	26	27	28	29	30
31						

Click individual date to select that date only. Click the appropriate weekday Header to select all occurrences of that weekday.

- **Selecting days of the week:** Click the day of the week heading link (the month is irrelevant, the day of the week will always repeat):



See also

- ▶ The *Creating an alias* recipe
- ▶ The *Creating a NAT port forward rule* recipe
- ▶ The *Creating a firewall rule* recipe

Remote desktop access, a complete example

The recipe describes how to access an internal machine using Microsoft's Remote Desktop Protocol (RDP).

Getting ready

The purpose of this recipe is to demonstrate a typical firewall task from start to finish. The following example will demonstrate how to remote into an internal machine from anywhere on the Internet. Doing so requires the configuration of the following features, which have all been covered in recipes preceding this point in the book:

- ▶ DHCP Server
- ▶ DHCP static mappings
- ▶ DNS Forwarder
- ▶ Aliases
- ▶ NAT port forwarding
- ▶ Firewall rules
- Schedules

How to do it...

1. Let's connect a computer to our network.
2. Browse to **Status | DHCP Leases** to find the newly added computer. Click the "plus" button to assign a new static mapping for the device:

Status: DHCP leases

IP address	MAC address	Hostname	Start	End	Online	Lease Type
192.168.1.199	00:1e:37:8a:cc:43	t61p	2000/03/06 05:35:18	2000/03/06 07:35:18	online	active

Show all configured leases

add a static mapping for this MAC address

3. Let's assign it a static IP address of **192.168.1.200** and call it **laptop1**:


Services: DHCP: Edit static mapping

Static DHCP Mapping

MAC address	<input type="text" value="00:1e:37:8a:cc:43"/> Copy my MAC address <small>Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx</small>
IP address	<input type="text" value="192.168.1.200"/> <small>If no IP address is given, one will be dynamically allocated from the pool.</small>
Hostname	<input type="text" value="laptop1"/> <small>Name of the host, without domain part.</small>
Description	<input type="text" value="Lenovo T61p Thinkpad Laptop"/> <small>You may enter a description here for your reference (not parsed).</small>

Save Cancel

4. Let's make sure our DNS Forwarder is configured to automatically serve static mappings at **Services | DNS Forwarder**, so that we can easily reference our laptop computer by name:

Services: DNS forwarder 


☒ **Enable DNS forwarder**

☐ **Register DHCP leases in DNS forwarder**
 If this option is set, then machines that specify their hostname when requesting a DHCP lease will be registered in the DNS forwarder, so that their name can be resolved. You should also set the domain in **System: General setup** to the proper value.


☒ **Register DHCP static mappings in DNS forwarder**
 If this option is set, then DHCP static mappings will be registered in the DNS forwarder, so that their name can be resolved. You should also set the domain in **System: General setup** to the proper value.


Save

5. Let's create an alias to be used when referencing this machine within pfSense from **Firewall | Aliases**:

Firewall: Aliases: Edit 

Alias Edit

Name  laptop1
 The name of the alias may only consist of the characters "a-z, A-Z and 0-9".

Description  My Thinkpad laptop.
 You may enter a description here for your reference (not parsed).

Type Host(s) ▼

Host(s)
 Enter as many hosts as you would like. Hosts must be specified by their IP address.

IP	Description
192.168.1.200	

Save **Cancel**

6. Let's create a schedule at **Firewall | Schedules** so that remote access is only enabled while we're at work, since that's when we intend to use it. Also, we can rest a little easier that it's not susceptible to attack while we're sleeping:

Name	Time Range(s)	Description
WorkHours	Mon - Fri 9:00-17:00	Regular work week hours.

- Let's create a NAT rule to forward all remote desktop (RDP) requests to our laptop from **Firewall | NAT**. From researching on "remote desktop protocol" on the Internet, we know we are dealing with TCP port 3389 (PfSense includes a predefined MS RDP port because it's so common):

Port Forward 1:1 Outbound									
	If	Proto	Src. addr	Src. ports	Dest. addr	Dest. ports	NAT IP	NAT Ports	Description
<input type="checkbox"/>	WAN	TCP	*	*	WAN address	3389 (MS RDP)	Laptop1	3389 (MS RDP)	Forward RDP to Laptop RDP

- Next, we need to add our schedule to the firewall rule that was automatically created from **Firewall | Rules**:

Floating WAN LAN DMZ										
	ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description
<input checked="" type="checkbox"/>		*	RFC 1918 networks	*	*	*	*	*		Block private networks
<input checked="" type="checkbox"/>		*	Reserved/not assigned by IANA	*	*	*	*	*	*	Block bogon networks
<input type="checkbox"/>		TCP	*	*	Laptop1	3389 (MS RDP)	*	none	<input checked="" type="checkbox"/> WorkHours	NAT Forward RDP to Laptop RDP

- Save** all changes.
- Apply** all changes, if necessary.

How it works...

Our NAT rule forwards all RDP requests to our laptop. The NAT rule is always enabled. Our firewall rule allows anyone to remote into our laptop, but only during work hours (Monday-Friday, 9am-5pm). At the time of writing this book, it's Sunday at 4 pm; so you can see the rule is correctly disabled.

There's more...

If we really wanted to tighten security, we could restrict external access to only our IP address at work. We would first create an alias for our office's IP address:

Firewall: Aliases: Edit

Alias Edit

Name

MyWorkIpAddress

The name of the alias may only consist of the characters "a-z, A-Z and 0-9".

Description

My company's public IP address.

You may enter a description here for your reference (not parsed).

Type

Host(s)

Host(s)

Enter as many hosts as you would like. Hosts must be specified by their IP address.

IP	Description
66.44.33.123	Entry added Mon, 06 Mar 2000 08:49:05 -0500

Save

Cancel





Then we would modify our firewall rule to only apply to requests coming from our company's IP address (remember, traffic that doesn't match any rules is blocked by default). Now, with pfSense's Filter Rule Association, we won't be able to modify the **Source** of our firewall rule directly.

Associated filter rule	<p>NOTE: This is associated to a NAT rule. You cannot edit the interface, protocol, source, or destination of associated filter rules.</p> <p>View the NAT rule</p>
Interface	<div>WAN</div> <p>Choose on which interface packets must come in to match this rule.</p>
Protocol	<div>TCP</div> <p>Choose which IP protocol this rule should match. Hint: in most cases, you should specify <i>TCP</i> here.</p>

So, we'll modify the NAT rule instead. From Source, click the **Advanced** option and specify the alias for our company's public IP address.

<div>Port Forward</div> <div>1:1</div> <div>Outbound</div>									
	If	Proto	Src. addr	Src. ports	Dest. addr	Dest. ports	NAT IP	NAT Ports	Description
<input type="checkbox"/>	WAN	TCP	MyWorkIpAddress	*	WAN address	3389 (MS RDP)	Laptop1	3389 (MS RDP)	Forward RDP to Laptop RDP

Then we'll double check if those changes have propagated down to our firewall rule, which they have:

Floating										WAN	LAN	DMZ
	ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description		
		*	RFC 1918 networks	*	*	*	*	*		Block private networks		
		*	Reserved/not assigned by IANA	*	*	*	*	*	*	Block bogon networks		
		TCP	<u>MyWorkIpAddress</u>	*	<u>Laptop1</u>	3389 (MS RDP)	*	none	 <u>WorkHours</u>	NAT Forward RDP to Laptop RDP		

See also

- ▶ The *Configuring DHCP servers* recipe in *Chapter 2, Essential Services*
- ▶ The *Creating static DHCP mappings* recipe in *Chapter 2, Essential Services*
- ▶ The *Configuring dynamic DNS* recipe in *Chapter 2, Essential Services*
- ▶ The *Creating an alias* recipe
- ▶ The *Creating a NAT port forward rule* recipe
- ▶ The *Creating a firewall rule* recipe
- ▶ The *Creating a schedule* recipe

4

Virtual Private Networking

In this chapter, we will cover:

- ▶ Creating an IPsec VPN tunnel
- ▶ Configuring the L2TP VPN service
- ▶ Configuring the OpenVPN service
- ▶ Configuring the PPTP VPN service

Introduction

Virtual Private Networking (VPN) is a cornerstone of modern computer systems. A VPN connection allows a remote user to securely connect to a network and access resources as if he were connected locally.

Like all great things, there are a variety of VPN services out there and pfSense has four most popular implementations built right in. **OpenVPN** is emerging as the standard VPN protocol, but be aware that you'll have to download client software for any Microsoft machine (OpenVPN support isn't built into Windows). IPsec is more complex, but is also a very popular VPN implementation. PPTP and L2TP services are frequently getting replaced with the aforementioned alternatives, but their use is still widespread and everything you need to create a connection is built into most major operating systems.

This chapter describes how to configure pfSense to serve any or all of the four major VPN implementations—IPsec, L2TP, OpenVPN, and PPTP.

Creating an IPsec VPN tunnel

This recipe describes how to configure pfSense to establish a VPN link using an IPsec tunnel.

Getting ready

IPSec is often the preferred method for network-to-network (as opposed to client-to-network) connections. A typical scenario involves creating a permanent, secure connection between headquarters and a branch office.



Networks connected through VPN must use different subnets. For example, if both networks use the 192.168.1.0/24 subnet, then VPN will not work.

How to do it...

1. Browse to **VPN | Ipsec**.
2. Click the “plus” button to create an IPsec tunnel.
3. Specify the **Remote gateway**.
4. Add a **Description**:

VPN: IPsec: Edit Phase 1 S L ?

Tunnels Mobile clients Pre-shared keys

General information

Disabled ☐ **Disable this phase1 entry**
Set this option to disable this phase1 without removing it from the list.

Interface WAN
Select the interface for the local endpoint of this phase1 entry.

Remote gateway texas.example.com
Enter the public IP address or host name of the remote gateway

Description Tunnel to Houston office.
You may enter a description here for your reference (not parsed).

Phase 1 proposal (Authentication)

Authentication method Mutual PSK
Must match the setting chosen on the remote side.

Negotiation mode aggressive
Aggressive is more flexible, but less secure.

My identifier My IP address

Peer identifier Peer IP address

Pre-Shared Key secret
Input your pre-shared key string.

5. Enter a **Pre-Shared Key**.
6. **Save** the changes.
7. Check **Enable IPsec**.
8. **Save** the changes:

VPN: IPsec

Tunnels Mobile clients Pre-shared keys

☒ Enable IPsec

Save

Remote Gateway	Mode	P1 Protocol	P1 Transforms	P1 Description
WAN texas.example.com	aggressive	3DES	SHA1	Tunnel to Houston office.

+ Show 0 Phase-2 entries

Note:
You can check your IPsec status at [Status:IPsec](#).

9. **Apply** changes, if necessary.
10. Browse to **Firewall | Rules**.
11. Select the **IPsec** tab.
12. Click the “plus” button to add a new firewall rule.
13. Set **Destination** to the LAN subnet.
14. Set **Destination port** to **any**.
15. Add a **description**, such as **Allow IPsec traffic to LAN**.

Firewall: Rules

Floating WAN LAN PUB DMZ PPTP VPN IPsec

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description
1	TCP	*	*	LAN net	*	*	none		Allow IPsec traffic to LAN.

☒ pass
☐ pass (disabled)
 ☒ block
☐ block (disabled)
 ☒ reject
☐ reject (disabled)
 ☒ log
☐ log (disabled)

Hint:
Rules are evaluated on a first-match basis (i.e. the action of the first rule to match a packet will be executed). This means that if you use block rules, you'll have to pay attention to the rule order. Everything that isn't explicitly passed is blocked by default.
You may drag and drop rules using your mouse to reorder the rule ordering.

16. **Save** the changes.
17. **Apply** changes, if necessary.

How it works...

Once an IPsec tunnel is established, clients connected to either network will have access to each other as if they were connected on different subnets of the same physical network.

See also

- ▶ The *Configuring the L2TP VPN service* recipe
- ▶ The *Configuring the OpenVPN service* recipe
- ▶ The *Configuring the PPTP VPN service* recipe

Configuring the L2TP VPN service

This recipe describes how to set up pfSense as a L2TP VPN server.

Getting ready

It's important to understand that unlike the other VPN implementations, L2TP does *not* encrypt any data. L2TP is simply a method of encapsulation and should only be used over trusted networks, or in conjunction with IPsec. A major advantage of L2TP, however, is that it can be used with non-IP networks.



Networks connected through VPN must use different subnets. For example, if both networks use the 192.168.1.0/24 subnet, then VPN will not work.

How to do it...

1. Browse to **VPN | L2TP**.
2. On the **Configuration** tab, check **Enable L2TP Server**.
3. Specify an unused IP for the **Server address**.
4. Specify an unused starting IP for the **Remote address range**. The range will be as long as the number of users specified in step 6.
5. Specify a **Subnet mask**.
6. Specify **Number of L2TP users**:

VPN: L2TP: L2TP ?

Configuration **Users**

☐ Off

☒ Enable l2tp server

Interface WAN

Server address 192.168.3.254
Enter the IP address the L2TP server should use on its side for all clients.

Remote address range 192.168.3.0
Specify the starting address for the client IP address subnet.

Subnet netmask 24
Hint: 24 is 255.255.255.0

Number of L2TP users 100
Hint: 10 is ten L2TP clients

7. **Save** the changes.
8. Click the **Users** tab.
9. Click the “plus” button to create a new user.
10. Specify a **username** and **password**:

VPN: L2TP: User: Edit ?

Username john DOE

Password ••••••••
•••••••• (confirmation)
 If you want to change the users password, enter it here twice.

IP address
 If you want the user to be assigned a specific IP address, enter it here.




Save **Cancel**

11. Save the changes:

VPN: L2TP: Users ?

Configuration **Users**

Username	IP address
john DOE	Dynamic

12. Browse to **Firewall | Rules**.
13. Select the **L2TP VPN** tab.
14. Click the “plus” button to create a new firewall rule.
15. Set the **Destination** to the LAN subnet.
16. Set the **Destination port range** to **any**.
17. Enter a **Description**, such as **Allow L2TP Clients to LAN**.
18. **Save** the changes:



19. **Apply** changes, if necessary.

How it works...

The L2TP service allows external users to remotely access a network interface of our choice. Users connected to our network using an L2TP VPN client will have access to the network as if they were on physically connected clients.


Connecting from a Windows 7 client

To create a L2TP VPN connection from a Windows 7 machine:


1. Open **Control Panel | Network and Internet | View network status and tasks** (opens Network and Sharing Center):




2. Click **Set up a new connection or network**:



3. Choose **Connect to a workplace** (dial-up or VPN connection):



4. Choose **Use my Internet connection (VPN)**:



5. Enter the **Server Address** we configured for the network we're connecting to. (If the L2TP server address you configured isn't directly accessible, you will have to NAT port-forward L2TP traffic).

The screenshot shows the 'Connect to a Workplace' dialog box. The title bar says 'Connect to a Workplace'. The main heading is 'Type the Internet address to connect to'. Below this, it says 'Your network administrator can give you this address.' There are two text input fields: 'Internet address:' with the value 'matt.dyndns.org' and 'Destination name:' with the value 'Matt's Network'. Below these fields are three checkboxes: 'Use a smart card' (unchecked), 'Allow other people to use this connection' (checked), and 'Don't connect now; just set it up so I can connect later' (unchecked). The 'Allow other people to use this connection' checkbox has a subtext: 'This option allows anyone with access to this computer to use this connection.' At the bottom right are 'Next' and 'Cancel' buttons.

6. Enter the **username** and **password** if any:

The screenshot shows the 'Connect to a Workplace' dialog box. The title bar says 'Connect to a Workplace'. The main heading is 'Type your user name and password'. There are three text input fields: 'User name:' with the value 'johndoe', 'Password:' with masked characters (dots), and 'Domain (optional):' which is empty. Below the 'Password:' field are two checkboxes: 'Show characters' (unchecked) and 'Remember this password' (unchecked). At the bottom right are 'Connect' and 'Cancel' buttons.

7. **Connect!** Windows will automatically detect whether the server is accepting L2TP or PPTP connections and configure itself accordingly.

See also


- ▶ The *Creating a NAT port forward rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Creating an IPsec VPN tunnel* recipe
- ▶ The *Configuring the OpenVPN service* recipe
- ▶ The *Configuring the PPTP VPN service* recipe

Configuring the OpenVPN service

This recipe describes how to configure pfSense to accept OpenVPN connections.

How to do it...

1. Browse to **VPN | OpenVPN**.
2. Click the **Wizards** tab.
3. Select **Local User Access** for **Type of Server**:



4. Click **Next**.
5. Enter a **Descriptive name** such as **MyCaCert** for the new CA certificate.
6. Enter **US** for **Country Code**.
7. Enter a **State or Province**, such as **New York**.
8. Enter a **City**, such as **New York**.
9. Enter an **Organization**, such as **Blue Key Consulting**.
10. Enter an **E-mail** address, such as **contact@example.com**.
11. Click the **Add new CA** button:

OpenVPN Remote Access Server Setup Wizard	
Create a New Certificate Authority (CA) Certificate	
Descriptive name:	<input type="text" value="MyCaCert"/> A name for your reference, to identify this certificate. This is the same as common-name field for other Certificates.
Key length:	<input type="text" value="2048 bit"/> Size of the key which will be generated. The larger the key, the more security is offers, but larger keys are generally slower to use.
Lifetime:	<input type="text" value="3650"/> Lifetime in days. This is commonly set to 3650 (Approximately 10 years.)
Country Code:	<input type="text" value="US"/> Two-letter ISO country code (e.g. US, AU, CA)
State or Province:	<input type="text" value="New York"/> Full State of Province name, not abbreviated (e.g. Kentucky, Indiana, Ontario).
City:	<input type="text" value="New York"/> City or other Locality name (e.g. Louisville, Indianapolis, Toronto).
Organization:	<input type="text" value="Blue Key Consulting"/> Organization name, often the Company or Group name.
E-mail:	<input type="text" value="contact@example.com"/> E-mail address for the Certificate contact. Often the e-mail of the person generating the certificate (i.e. You.)
<input type="button" value="Add new CA"/>	

12. Enter a **Descriptive name** for the new Server certificate, **MyServerCert**. Creating a server certificate will look almost identical to the CA certificate you created in the previous step.
13. Enter **US** for **Country Code**.
14. Enter a **State or Province**, such as **New York**.
15. Enter a **City**, such as **New York**.
16. Enter an **Organization**, such as **Blue Key Consulting**.
17. Enter an **E-mail** address, such as **contact@example.com**.

18. Click the **Create new Certificate** button:

OpenVPN Remote Access Server Setup Wizard	
Create a New Server Certificate	
Descriptive name:	<input type="text" value="MyServerCert"/> A name for your reference, to identify this certificate. This is also known as the certificate's "Common Name."
Key length:	<input type="text" value="2048 bits"/> Size of the key which will be generated. The larger the key, the more security it offers, but larger keys are generally slower to use.
Lifetime:	<input type="text" value="3650"/> Lifetime in days. This is commonly set to 3650 (Approximately 10 years.)
Country Code:	<input type="text" value="US"/> Two-letter ISO country code (e.g. US, AU, CA)
State or Province:	<input type="text" value="New York"/> Full State or Province name, not abbreviated (e.g. Kentucky, Indiana, Ontario).
City:	<input type="text" value="New York"/> City or other Locality name (e.g. Louisville, Indianapolis, Toronto).
Organization:	<input type="text" value="Blue Key Consulting"/> Organization name, often the Company or Group name.
E-mail:	<input type="text" value="contact@example.com"/> E-mail address for the Certificate contact. Often the e-mail of the person generating the certificate (i.e. You.)
<input type="button" value="Create new Certificate"/>	

19. Specify a **description**, such as **My OpenVPN Connection**:

General OpenVPN Server Information	
Interface:	<input type="text" value="wan"/> The interface where OpenVPN will listen for incoming connections (typically WAN.)
Protocol:	<input type="text" value="UDP"/> Protocol to use for OpenVPN connections. If you are unsure, leave this set to UDP.
Local Port:	<input type="text" value="1194"/> Local port upon which OpenVPN will listen for connections. The default port is 1194. Leave this blank unless you need to use a different port.
Description:	<input type="text" value="My OpenVPN Connection"/> A name for this OpenVPN instance, for your reference. It can be set however you like, but is often used to distinguish the purpose of the service (e.g. "Remote Technical Staff").


20. Specify a **Tunnel Network** in CIDR notation. This should be an unused interface range (that, of course, doesn't overlap with the existing LAN) such as **192.168.4.0/24**.
21. Specify the **Local Network**, in CIDR notation that clients will be able to access. This is generally our LAN network, **192.168.1.0/24**.
22. Specify a maximum number of **Concurrent Connections**:

Tunnel Settings	
Tunnel Network:	<input type="text" value="192.168.4.0/24"/> <small>This is the virtual network used for private communications between this server and client hosts expressed using CIDR notation (eg. 10.0.8.0/24). The first network address will be assigned to the server virtual interface. The remaining network addresses can optionally be assigned to connecting clients. (see Address Pool)</small>
Redirect Gateway:	<input type="checkbox"/> Force all client generated traffic through the tunnel.
Local Network:	<input type="text" value="192.168.1.0/24"/> <small>This is the network that will be accessible from the remote endpoint, expressed as a CIDR range. You may leave this blank if you don't want to add a route to the local network through this tunnel on the remote machine. This is generally set to your LAN network.</small>
Concurrent Connections:	<input type="text" value="100"/> <small>Specify the maximum number of clients allowed to concurrently connect to this server.</small>
Compression:	<input type="checkbox"/> Compress tunnel packets using the LZO algorithm.
Type-of-Service:	<input type="checkbox"/> Set the TOS IP header value of tunnel packets to match the encapsulated packet value.
Inter-Client Communication:	<input type="checkbox"/> Allow communication between clients connected to this server.
Duplicate Connections:	<input type="checkbox"/> Allow multiple concurrent connections from clients using the same Common Name. <small>NOTE: This is not generally recommended, but may be needed for some scenarios.</small>

23. Click the **Next** button.
24. Check **Add a rule to permit traffic from clients on the Internet to the OpenVPN server process**.
25. Check **Add a rule to allow all traffic from connected clients to pass across the VPN tunnel**:

OpenVPN Remote Access Server Setup Wizard	
Firewall Rule Configuration	
<small>Firewall Rules control what network traffic is permitted. You must add rules to allow traffic to the OpenVPN server's IP and port, as well as allowing traffic from connected clients through the tunnel. These rules can be automatically added here, or configured manually after completing the wizard.</small>	
Traffic from clients to server	
Firewall Rule:	<input checked="" type="checkbox"/> Add a rule to permit traffic from clients on the Internet to the OpenVPN server process.
Traffic from clients through VPN	
OpenVPN rule:	<input checked="" type="checkbox"/> Add a rule to allow all traffic from connected clients to pass across the VPN tunnel.
<input type="button" value="Next"/>	

26. Click **Next**:



27. Click on **Finish**:



How it works...

The OpenVPN service allows external users to establish a secure, encrypted connection to our network. Users will connect to the network using an OpenVPN client and once authenticated, the user will have access to the network as if they were physically connected.

Encryption algorithms

Choosing the correct encryption algorithm for your hardware is critical for maximum hardware performance. Many VPN expansion cards, such as those found on Netgate systems using Alix boards require AES-128-CBC. Check with your hardware vendor for details.


OpenVPN Client Export

There is a pfSense package called the **OpenVPN Client Export Utility** that simplifies the client configuration process. To install it:

1. Browse to **System | Packages**.
2. Click the **Available Packages** tab.
3. Locate the **OpenVPN Client Export Utility** and click the “plus” button to begin installation:

OpenVPN Client Export Utility	Security	BETA 0.5 platform: 2.0	No info, check the forum	Allows a pre-configured OpenVPN Windows Client or or Mac OSX's Viscosity configuration bundle to be exported directly from pfSense.	
-------------------------------	----------	---------------------------------	--------------------------	---	---

4. The package will be downloaded and installed automatically.



5. The plugin will be installed to the **VPN | OpenVPN** menu.

See also

- ▶ The *Creating an IPsec VPN tunnel* recipe
- ▶ The *Configuring the L2TP VPN service* recipe
- ▶ The *Configuring the PPTP VPN service* recipe

Configuring the PPTP VPN service

This recipe describes how to configure pfSense to accept PPTP VPN connections.

How to do it...

1. Browse to the **VPN | PPTP | Configuration** tab.
2. Check **Enable PPTP server**.
3. Choose **No. PPTP users**.
4. Enter an unused IP address to specify as the PPTP **Server address**. PfSense's PPTP service will listen on this address.
5. Enter the start of the **Remote address range** for clients that connect. Remember, a valid range must be large enough for the number of users specified above.

VPN: VPN PPTP

Configuration **Users**

☐ Off

☐ Redirect incoming PPTP connections to:

PPTP redirection
Enter the IP address of a host which will accept incoming PPTP connections.

☒ Enable PPTP server

No. PPTP users
Hint: 10 is TEN pptp clients

Server address
Enter the IP address the PPTP server should use on its side for all clients.

Remote address range
Specify the starting address for the client IP subnet.

PPTP DNS Servers

primary and secondary DNS servers assigned to PPTP clients

WINS Server

6. Check **Require 128-bit encryption**:

☒ **Require 128-bit encryption**
 When set, only 128-bit encryption will be accepted. Otherwise 40-bit and 56-bit encryption will be accepted as well. Note that encryption will always be forced on PPTP connections (i.e. unencrypted connections will not be accepted).

Save

Note:
 don't forget to add a firewall rule to permit traffic from PPTP clients!

7. **Save** the changes.
8. Select the **Users** tab.
9. Click the “plus” button to add a user.
10. Specify **Username** and **Password**.
11. **Save** the changes:

VPN: VPN PPTP: Users

Configuration **Users**

Username	IP address
john doe	

12. Browse to **Firewall | Rules**.
13. Select the **PPTP VPN** tab.
14. Click the “plus” button to create a new firewall rule.
15. Set the **Destination** to LAN subnet.
16. Set the **Destination port range** to **any**.
17. Enter a **Description**, such as **Allow PPTP Clients to LAN**.
18. **Save** the changes:

Firewall: Rules

Floating **WAN** **LAN** **PUB** **DMZ** **PPTP VPN**

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description
1	TCP	*	*	LAN net	*	*	none		Allow PPTP clients to LAN.

☒ pass
☐ pass (disabled)
 ☒ block
☐ block (disabled)
 ☒ reject
☐ reject (disabled)
 ☒ log
☐ log (disabled)

19. **Apply** changes, if necessary.

How it works...

The PPTP service allows external users to establish a secure, encrypted connection to our network. Users will connect to the network using a PPTP client and, once authenticated, the user will have access to the network as if they were physically connected.


Connecting from a Windows 7 client

Perform the following steps to create a PPTP VPN connection from a Windows 7 machine:


1. Open **Control Panel | Network and Internet | View network status and tasks** (opens Network and Sharing Center):




2. Click **Set up a new connection or network**:




3. Choose **Connect to a workplace** (dial-up or VPN connection):



4. Choose **Use my Internet connection (VPN)**:



5. Enter the public IP address or hostname of the network we're connecting to:



6. Enter the **User name** and **Password** you've configured:




7. Click on **Connect**! Windows will automatically detect whether the server is accepting PPTP or L2TP connections and configure itself accordingly.


Connecting from a Ubuntu 10.10 client

Perform the following steps to create a PPTP VPN connection from a Ubuntu machine:

1. Open **System | Preferences | Network Connections**.
2. Choose **VPN** tab | **Add** button to create a new VPN connection.




3. Select **PPTP** and click the **Create...** button.



4. Add a **Connection name**. I'll call it **Matt's Network**.
5. Add a **Gateway**, this should resolve to the server IP you configured during PPTP setup. If the IP isn't directly accessible, you'll have to configure a NAT port forward rule.
6. Add the **User name** and **Password** you've configured:



7. Click **Apply**.
8. Click **Close**.
9. Pull down the **Network connection** toolbar menu and choose **VPN Connections** | **Matt's Network**:




Connect from an Apple Mac OSx Client

Perform the following steps to create a PPTP VPN connection from a Mac OSx machine:


1. Open **System Preferences**:



2. Click **Network**:



3. Click the “plus” button to add a new network connection.
4. Select the **VPN** as the **Interface**.
5. Select the **PPTP** as the **VPN Type**.
6. Create a **Service Name**, **Matt's Network**:



7. Specify **Server Address**, this should resolve to the Server IP you configured during PPTP setup. If the IP isn't directly accessible you'll have to configure a NAT port-forward rule.
8. Enter the username we'd configured in **Account Name**.
9. Click **Connect** and the password prompt will appear.



See also

- ▶ The *Creating a NAT port forward rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Creating an IPsec VPN tunnel* recipe
- ▶ The *Configuring the L2TP VPN service* recipe
- ▶ The *Configuring the OpenVPN service* recipe

5

Advanced Configuration

In this chapter, we will cover:

- ▶ Creating a virtual IP
- ▶ Creating a 1:1 NAT rule
- ▶ Creating an outbound NAT rule
- ▶ Creating a gateway
- ▶ Creating a static route
- ▶ Configuring traffic-shaping (QoS, Quality of Service)
- ▶ Bridging interfaces
- ▶ Creating a virtual LAN
- ▶ Creating a captive portal

Introduction

The following recipes cover advanced networking features that are usually found only in enterprise-class software. However, every single one of these features is available in the latest version of pfSense.

Creating a virtual IP

This recipe describes how to create a virtual IP address in pfSense.

Getting ready

pfSense allows for four different types of virtual IP addresses to be created:

- ▶ **Proxy ARP**
- ▶ **CARP**
- ▶ **Other**
- ▶ **IP Alias**


A common use of virtual IPs is to configure a 1:1 NAT relationship. In this scenario a virtual IP of type **Other** is required, which we will configure in this recipe.

How to do it...

1. Browse to **Firewall | Virtual IPs**.
2. Click the "plus" button to add a new virtual IP address.
3. Choose **Other** as **Type**.
4. Select the **WAN** as the **Interface**.
5. Specify the **IP Address**.
6. Add a **Description**.

Firewall: Virtual IP Address: Edit	
Edit Virtual IP	
Type	<input type="radio"/> Proxy ARP <input type="radio"/> CARP <input checked="" type="radio"/> Other <input type="radio"/> IP Alias
Interface	WAN
IP Address(es)	Type: Single address Address: 66.77.88.99 / 32
Virtual IP Password	<input type="text"/> Enter the VHID group password.
VHID Group	1 Enter the VHID group that the machines will share
Advertising Frequency	0 The frequency that this machine will advertise. 0 = master. Anything above 0 designates a backup.
Description	<input type="text" value="My Other VIP."/> You may enter a description here for your reference (not parsed).
<input type="button" value="Save"/> <input type="button" value="Cancel"/>	

7. **Save** the changes.
8. **Apply** changes, if necessary.



How it works...

A virtual IP (VIP) of type **Other** has the following properties:

- ▶ Traffic can only be forwarded to this type of VIP; pfSense cannot use this type of VIP for its own services
- ▶ The VIP may be in a different subnet than its interface
- ▶ The VIP cannot respond to pings

There's more...

We've configured a virtual IP of type **Other**, but there are three more types of virtual IP addresses that can be configured in pfSense 2.0. The four different types of virtual IP addresses are similar, but have slightly varied properties:

- ▶ **CARP**
 - ❑ Can be used or forwarded by the firewall
 - ❑ Uses Layer 2 traffic
 - ❑ Should be used in firewall fail-over or load-balancing scenarios
 - ❑ Must be in the same subnet as the interface
 - ❑ Will respond to pings if configured properly
- ▶ **Proxy ARP**
 - ❑ Can only be forwarded by the firewall
 - ❑ Uses Layer 2 traffic
 - ❑ Can be in a different subnet than the interface
 - ❑ Cannot respond to pings

► **Other**

- ❑ Can only be forwarded by the firewall
- ❑ Can be in a different subnet than the interface
- ❑ Cannot respond to pings

► **IP Alias**

- ❑ New to pfSense 2.0
- ❑ Can be used or forwarded by the firewall
- ❑ Allows extra IP addresses to be added to an interface

Configuring a CARP virtual IP address

1. Browse to **Firewall | Virtual IPs**.
2. Click the "plus" button to add a new virtual IP address.
3. Choose **CARP** as **Type**.
4. Select **WAN** as the **Interface**.
5. Specify an **IP Address**.
6. Specify a **Virtual IP Password**.
7. Choose a **VHID Group**.
8. Choose an **Advertising Frequency** (**0** for **master**).
9. Add a **Description**:

Firewall: Virtual IP Address: Edit

Edit Virtual IP

Type	<input type="radio"/> Proxy ARP <input checked="" type="radio"/> CARP <input type="radio"/> Other <input type="radio"/> IP Alias
Interface	WAN ▼
IP Address(es)	Type: Single address Address: 69.116.129.1 / 32 ▼ <small>This must be the network's subnet mask. It does not specify a CIDR range.</small>
Virtual IP Password	Enter the VHID group password.
VHID Group	1 ▼ Enter the VHID group that the machines will share
Advertising Frequency	0 ▼ The frequency that this machine will advertise. 0 = master. Anything above 0 designates a backup.
Description	My CARP VIP. You may enter a description here for your reference (not parsed).

Save Cancel

10. **Save** the changes.
11. **Apply** changes, if necessary.

Firewall: Virtual IP Addresses

Virtual IPs
CARP Settings

Virtual IP address	Type	Description
66.77.88.99/32	IP	My Other VIP.
69.116.129.1/32 (vhid 1)	CARP	My CARP VIP.

Note:
The virtual IP addresses defined on this page may be used in NAT mappings.
You can check the status of your CARP Virtual IPs and interfaces [here](#).

Configuring a Proxy ARP virtual IP address

1. Browse to **Firewall | Virtual IPs**.
2. Click the "plus" button to add a new virtual IP address.
3. Choose **Proxy ARP** as **Type**.
4. Select **WAN** as the **Interface**.
5. Select **Single address** as the **Type** of **IP Address**.
6. Specify an **IP Address**.
7. Add a **Description**:

Firewall: Virtual IP Address: Edit

Edit Virtual IP

Type
☒ Proxy ARP
☐ CARP
☐ Other
☐ IP Alias

Interface
WAN

IP Address(es)
Type: Single address
Address: 55.44.33.22 / 32 This is a CIDR block of proxy ARP addresses.

Virtual IP Password
Enter the VHID group password.

VHID Group
1
Enter the VHID group that the machines will share

Advertising Frequency
0
The frequency that this machine will advertise. 0 = master. Anything above 0 designates a backup.

Description
My Proxy ARP VIP.
You may enter a description here for your reference (not parsed).

Save Cancel

8. **Save** the changes.
9. **Apply** changes, if necessary.

Firewall: Virtual IP Addresses

Virtual IPs
CARP Settings

Virtual IP address	Type	Description
66.77.88.99/32	IP	My Other VIP.
69.116.129.1/32 (vhid 1)	CARP	My CARP VIP.
55.44.33.22/32	P ARP	My Proxy ARP VIP.

Note:
The virtual IP addresses defined on this page may be used in NAT mappings. You can check the status of your CARP Virtual IPs and interfaces here.

Configuring an IP alias virtual IP address

1. Browse to **Firewall | Virtual IPs**.
2. Click the "plus" button to add a new virtual IP address.
3. Choose **IP Alias Type**.
4. Select the **WAN Interface**.
5. Specify an **IP Address**.
6. Add a **Description**:

Firewall: Virtual IP Address: Edit

Edit Virtual IP

Type
☐ Proxy ARP
☐ CARP
☐ Other
☒ IP Alias

Interface
WAN

IP Address(es)
Type: Single address
Address: 22.33.44.55 / 32 This must be the network's subnet mask. It does not specify a CIDR range.

Virtual IP Password
Enter the VHID group password.

VHID Group
1
Enter the VHID group that the machines will share

Advertising Frequency
0
The frequency that this machine will advertise. 0 = master. Anything above 0 designates a backup.

Description
My IP Alias VIP.
You may enter a description here for your reference (not parsed).

Save Cancel

7. **Save** the changes.
8. **Apply** changes, if necessary.

Firewall: Virtual IP Addresses

Virtual IPs
CARP Settings

Virtual IP address	Type	Description
66.77.88.99/32	IP	My Other VIP.
69.116.129.1/32 (vhid 1)	CARP	My CARP VIP.
55.44.33.22/32	P ARP	My Proxy ARP VIP.
22.33.44.55/32	II Alias	My IP Alias VIP.

Note:
The virtual IP addresses defined on this page may be used in NAT mappings. You can check the status of your CARP Virtual IPs and interfaces here.

See also

- ▶ The *Configuring a 1:1 NAT rule* recipe
- ▶ The *Creating an outbound NAT rule* recipe
- ▶ The *Creating a static route* recipe
- ▶ The *Creating a virtual LAN* recipe

Configuring a 1:1 NAT rule

This recipe describes how to configure a 1:1 NAT rule. A **1:1 NAT rule** is used when you want to associate a public IP address with a single internal machine. Everything destined for the public IP will be routed to a single internal machine.

How to do it...

1. Browse to **Firewall | Virtual IPs**.
2. On the **Virtual IPs** tab, click the "plus" button to add a new virtual IP Address.
3. Select the **Proxy ARP** as the **Type**.
4. Select **WAN** as the **Interface**.
5. Select **Single address** as the **Type** of **IP Address** and specify our external public IP address.

6. Add a **Description**, such as **My public IP address**:

Firewall: Virtual IP Addresses ?

Virtual IPs
CARP Settings

Virtual IP address	Type	Description	
92.44.66.77/32	P ARP	My public IP address.	<div style="display: flex; justify-content: space-around; align-items: center;"> + ✖ </div>

Note:
 The virtual IP addresses defined on this page may be used in NAT mappings.
 You can check the status of your CARP Virtual IPs and interfaces [here](#).

7. **Save** the changes.
8. **Apply** changes, if necessary.
9. Browse to **Firewall | NAT**.
10. Select the **1:1** tab.
11. Click the "plus" button to add a new 1:1 NAT rule.
12. Select an **Interface**, in this case **WAN**.
13. Specify a **Source**, in this case **any**.
14. Specify a **Destination**, we'll specify our internal webserver by alias.
15. Specify the **External subnet**, our public IP address.
16. Add a **Description**, such as **Forward all external requests to Webserver1**.
17. Leave **NAT reflection** disabled:

Firewall: NAT: 1:1: Edit

Edit NAT 1:1 entry

Disabled ☐ **Disable this rule**
Set this option to disable this rule without removing it from the list.

Interface WAN ▾
Choose which interface this rule applies to.
Hint: in most cases, you'll want to use WAN here.

Source ☐ **not**
Use this option to invert the sense of the match.
Type: any ▾
Address: / 31
Enter the internal (LAN) subnet for the 1:1 mapping. The subnet size specified for the external subnet also applies to the internal subnet (they have to be the same).

Destination ☐ **not**
Use this option to invert the sense of the match.
Type: Single host or alias ▾
Address: Webserver1 / 31

External subnet 92.44.66.77

Description Forward all external requests to Webserver1.
You may enter a description here for your reference (not parsed).

NAT reflection disable ▾

Save Cancel

18. **Save** the changes.

19. **Apply** changes, if necessary.

How it works...

Once a 1:1 NAT relationship is established, all traffic will be forwarded to the internal IP address (or subnet), just as if the internal machine was directly configured with the public IP address. This is much easier than creating port-forward rules if all of your incoming traffic is destined for the same machine.

There's more...

Like many advanced networking features, 1:1 NAT relationships require the use of Virtual IP Addresses (VIPs).

See also

- ▶ The *Creating a virtual IP* recipe

Creating an outbound NAT rule

This recipe describes how to create an outbound NAT rule.

Getting ready

An outbound NAT rule defines how traffic *leaving* a network will be translated. This can be a difficult concept to grasp at first since most general networking scenarios are only concerned with where network packets are headed, not what they look like when they leave.

This recipe will describe how to use an outbound NAT rule to solve a common scenario which involves NATing to a single machine with multiple interfaces. We will assume that we have a single destination server with two interfaces—LAN and DMZ, and our pfSense firewall is protecting both interfaces. Using a regular old port-forward rule, we forward HTTP requests to the server on its DMZ interface, which is fine. However, when we try to forward SSH requests to the LAN interface of the server, traffic arrives correctly but tries to reply via the DMZ network. This fails to be recognized as valid by the firewall and we're left with a timeout when trying to connect.





The solution is to handle the SSH requests using an outbound NAT rule coupled with a 1:1 NAT rule, as described in the recipe.

How to do it...

1. Browse to **Firewall | Virtual IPs**.
2. On the **Virtual IPs** tab, click the "plus" button to add a new virtual IP address.
3. Select the **Proxy ARP** as the **Type**.
4. Select **WAN** as the **Interface**.
5. Select **Single address** as the **Type** of **IP Address** and specify our external public IP address.
6. Add a **Description**, such as **My public IP address**.
7. **Save** the changes.
8. **Apply** changes, if necessary.

Firewall: Virtual IP Addresses

Virtual IPs
CARP Settings

Virtual IP address	Type	Description	
92.44.66.77/32	 CARP	My public IP address.	  

Note:
The virtual IP addresses defined on this page may be used in NAT mappings.
You can check the status of your CARP Virtual IPs and interfaces [here](#).

9. Browse to **Firewall | NAT**.
10. Click the **Outbound** tab.
11. Select **Automatic outbound NAT rule generation (IPsec passthrough included)** mode.
12. Click the "plus" button to add a new outbound NAT mapping.
13. Choose the **Interface** of the machine(s) that will respond, in this case **LAN**.
14. Specify **any** for **Source**.
15. Specify a **Destination**, the IP address of the server that will respond.
16. Leave **Translation** set to **Interface address** and specify port **22** to respond to SSH requests.
17. Enter a **Description**, such as **Outbound NAT for WAN Clients to Server1 SSH**.
18. **Save** the changes.

19. **Apply** changes, if necessary.

Firewall: NAT: Outbound

Port Forward

1:1

Outbound

Mode:

☒ Automatic outbound NAT rule generation
(IPsec passthrough included)

☐ Manual Outbound NAT rule generation
(AON - Advanced Outbound NAT)

Save

Mappings:

	Interface	Source	Source Port	Destination	Destination Port	NAT Address	NAT Port	Static Port	Description
<input type="checkbox"/>	LAN	any	*	192.168.1.200/32	*	*	22	NO	Outbound NAT for WAN Clients to Server1 SSH

Note:

If advanced outbound NAT is enabled, no outbound NAT rules will be automatically generated any longer. Instead, only the mappings you specify below will be used. With advanced outbound NAT disabled, a mapping is automatically created for each interface's subnet (except WAN). If you use target addresses other than the WAN interface's IP address, then depending on the way your WAN connection is setup, you may also need a Virtual IP.

20. Browse to **Firewall | NAT**.

21. Click the **1:1** tab.

22. Click the "plus" button to add a new 1:1 NAT mapping.

23. Choose **WAN** as the **Interface**.

24. Select **any** for **Source**.

25. Specify a **Single host or Alias** for **Destination**, and provide the IP address of the server which will handle requests.

26. Specify the Virtual IP address we created earlier as the **External subnet**.

27. Add a **Description**, such as **1:1 NAT Public IP to Server1**.

28. **Save** the changes.

29. **Apply** changes, if necessary.

Firewall: NAT: 1:1 

Port Forward **1:1** Outbound

Interface	External IP	Source IP	Destination IP	Description			
WAN	92.44.66.77	*	192.168.1.200	1:1 NAT Public IP to Server1			

Note:
Depending on the way your WAN connection is setup, you may also need a Virtual IP.
If you add a 1:1 NAT entry for any of the interface IPs on this system, it will make this system inaccessible on that IP address. i.e. if you use your WAN IP address, any services on this system (IPsec, OpenVPN server, etc.) using the WAN IP address will no longer function.

30. Browse to **Firewall | Rules**.
31. Click the **WAN** tab.
32. Click the "plus" button to add a new firewall rule.
33. Choose **any** for **Source**.
34. Choose **any** for **Source port range**.
35. Select **Single host or Alias** for **Destination** and specify the IP address or alias of the server that will handle requests.
36. Specify **SSH** for our **Destination port range**.
37. Add a **Description**, such as **Allow WAN Clients to Server1 SSH**.
38. **Save** the changes.

39. **Apply** changes, if necessary.

Firewall: Rules S L ?

Floating **WAN** **LAN** **DMZ**

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description
	*	RFC 1918 networks	*	*	*	*	*		Block private networks
	*	Reserved/not assigned by IANA	*	*	*	*	*	*	Block bogon networks
	TCP	*	*	192.168.1.200	22 (SSH)	*	none		Allow WAN Clients to Server1 SSH

pass
 block
 reject
 log

pass (disabled)
 block (disabled)
 reject (disabled)
 log (disabled)

Hint:

Rules are evaluated on a first-match basis (i.e. the action of the first rule to match a packet will be executed). This means that if you use block rules, you'll have to pay attention to the rule order. Everything that isn't explicitly passed is blocked by default.

You may drag and drop rules using your mouse to reorder the rule ordering.

How it works...

The outbound rule we've created explicitly tells pfSense to direct outgoing traffic through the LAN interface, regardless of which interface it came in on. This will allow SSH traffic to find its way home even though the default gateway of the server is configured for another interface (the DMZ). Meanwhile, the HTTP requests that have been configured through port-forwarding will continue to function normally.

See also

- ▶ The *Creating a virtual IP* recipe
- ▶ The *Creating a 1:1 NAT rule* recipe
- ▶ The *Configuring a port-forward rule* recipe

Creating a gateway

This recipe describes how to create a gateway in pfSense.

Getting ready

Typically, networks with a single WAN connection will not need to modify gateway settings; the default will suffice. However, networks that have more than one internet connection or take advantage of certain advanced features (for example static routes) will need to define custom gateways.

How to do it...

1. Go to **System | Routing**.
2. Click the **Gateways** tab.
3. Click the "plus" button to add a new gateway.
4. Select the **Interface** for the new gateway.
5. Specify a **Name** for the gateway (no spaces allowed).
6. Specify the IP address for the gateway—it must be a valid address on the chosen interface.
7. We may assign an alternative **Monitor IP**, or leave it blank to be filled with the gateway's IP address by default.
8. Add a **Description**, such as **My new gateway**:

System: Gateways: Edit gateway
S ?

Edit gateway	
Interface	DM7 ▼ Choose which interface this gateway applies to.
Name	MyNewGateway Gateway name
Gateway	192.168.2.100 Gateway IP address
Default Gateway	<input type="checkbox"/> Default Gateway This will select the above gateway as the default gateway
Monitor IP	192.168.2.100 Alternative monitor IP Enter an alternative address here to be used to monitor the link. This is used for the quality RRD graphs as well as the load balancer entries. Use this if the gateway does not respond to ICMP echo requests (pings).
Advanced	Advanced - Show advanced option
Description	My new gateway. You may enter a description here for your reference (not parsed).

Save Cancel

9. **Save** the changes.
10. **Apply** changes, if necessary.

System: Gateways

Gateways Routes Groups

Name	Interface	Gateway	Monitor IP	Description
GW_WAN (default)	WAN	dynamic	dynamic	Interface wan Dynamic Gateway
MyNewGateway	DMZ	192.168.2.100	192.168.2.100	My new gateway.

How it works...

A gateway is the "portal" which connects two networks together. Traffic between two networks, such as between our LAN and the Internet, must pass through a gateway. If we had multiple WAN connections (that is multiple connections to the Internet) we would need to define gateways for each.

There's more...

As we'll see in the next recipe, gateways are necessary when creating static routes. A static route is a hard-coded pathway from one network to another, and all inter-network traffic must pass through a gateway.

Gateway Groups

PfSense 2.0 implements a new concept called Gateway Groups. A **Gateway Group** is a collection of gateways that can be treated as one unit from various other features in the system.

Gateway groups will appear in the gateway drop-down menu when appropriate, such as when defining a firewall rule.

See also

- ▶ The *Creating a firewall rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Configuring the WAN interface* recipe in *Chapter 1, Initial Configuration*
- ▶ The *Creating a static route* recipe

Creating a static route

This recipe describes how to create a static route using pfSense.

Getting ready

Static routes are for accessing networks that aren't reachable through the default WAN gateway, but can be reached indirectly through a difference interface. A common scenario might be an office building with a shared network for printing. Anyone connected to the business network can use the shared network, they just need to create a static route. We can use pfSense to create this static route for an entire interface, instead of a configuring a static route on each individual PC.

How to do it...

1. Browse to **System | Routing**.
2. Click the **Gateways** tab.
3. Click the "plus" button to add a new gateway.
4. Select the **Interface** for the new gateway.
5. Specify a **Name** for the gateway (no spaces allowed).
6. Specify the **IP address** for the gateway; it must be a valid address on the chosen interface.
7. We may assign an alternative **Monitor IP**, or leave blank to be filled with the gateway's IP address by default.
8. Add a **Description**, such as **My new gateway**.
9. **Save** the changes.
10. **Apply** changes, if necessary.

System: Gateways S ?

Gateways **Routes** **Groups**

Name	Interface	Gateway	Monitor IP	Description
GW_WAN (default)	WAN	dynamic	dynamic	Interface wan Dynamic Gateway
MyNewGateway	DMZ	192.168.2.100	192.168.2.100	My new gateway.

11. Browse to **System | Routing**.
12. Click the **Routes** tab.
13. Click the "plus" button to add a new route.
14. Enter the IP Address of the **Destination** network.
15. Choose the **Gateway** we've defined above.
16. Add a **Description**, such as **Static route for shared printer network**.

System: Static Routes: Edit route

Edit route entry

Destination network

192.168.2.0 / 24

Destination network for this static route

Gateway

MyNewGateway - 192.168.2.100

Choose which gateway this route applies to or add a new one.

Description

Static route for shared printer network.

You may enter a description here for your reference (not parsed).

Save
Cancel

17. **Save** the changes.
18. **Apply** changes, if necessary.

System: Static Routes

Gateways Routes Groups

Network	Gateway	Interface	Description
192.168.2.0/24	MyNewGateway - 192.168.2.100	DMZ	Static route for shared printer network.

Note: Do not enter static routes for networks assigned on any interface of this firewall. Static routes are only used for networks reachable via a different router, and not reachable via your default gateway.

How it works...

By defining a static route, we have hard-coded a path to our shared printer network. We can now access this network through this static route, and offer this gateway to other users of the firewall.

See also

- The *Creating a gateway* recipe

Configuring traffic-shaping (QoS, Quality of Service)

This recipe describes how to configure traffic-shaping in pfSense.

Getting ready

Traffic-shaping, also known as **Quality of Service (QoS)**, is the prioritization and throttling of network packets. Prioritizing network packets gives certain types of traffic precedence over others. Throttling network packets sets limits to the amount of certain types of traffic for any given time. An administrator may want to prioritize VoIP packets over all others to ensure phone calls aren't dropped or interrupted due to high network traffic. Additionally, we may also want to limit VoIP throughput to 100Kbps. This is a fairly typical example of shaping VoIP traffic

In the following recipe, we will use pfSense to shape the external Remote Desktop (MSRDP) connections coming into our network. This will ensure that we will be able to remotely administer our servers even under heavy loads.

How to do it...

1. Browse to **Firewall | Traffic Shaper**.
2. Click the **Wizards** tab.
3. Of the **Wizard functions**, click **Single WAN multi LAN**.

Firewall: Traffic Shaper: Wizards S ?

By Interface

By Queue

Limiter

Layer7

Wizards

Wizard function	Wizard Link
Single Lan multi Wan	traffic_shaper_wizard.xml
Single Wan multi Lan	traffic_shaper_wizard_multi_lan.xml
Multiple Lan/Wan	traffic_shaper_wizard_multi_all.xml
Dedicated Links	traffic_shaper_wizard_dedicated.xml

4. Enter our number of LAN type connections in **Enter number of LAN type connections**. Our pfSense box has a LAN and a DMZ; so we'll enter **2**.

This wizard will guide you through setting up the pfSense traffic shaper for the situation where you have 1 WAN connection and multiple LAN connections. Please be aware that Custom Bandwidths should not exceed 30% of the interface/link bandwidth. Keep this in mind during the wizard.

Enter number of LAN type connections: Number of local(LAN) interfaces you have

Next

5. Enter the **Link Upload** speed of our WAN connection. Our ISP provides us a 2,000Kbps (2Mbps) upload speed. Check <http://speedtest.net/> for an accurate measurement.
6. Enter the **Link Download** speed of our WAN connection. Our ISP provides us a 15,000Kbps (15Mbps) download speed. Check <http://speedtest.net/> for an accurate measurement.

pfSense Traffic Shaper Wizard

Setup WAN(upload) scheduler

Upload Scheduler: **HFSC** Queueing discipline to apply on the upload of this link.

Setup link speed details

Link Upload: **Kbit/s** Upload bandwidth on this connection.

Link Download: **Kbit/s** Download bandwidth on this connection.

Setup connection speed and scheduler information for LAN interface #1

LAN interface: **LAN** Interface of this connection.

LAN Scheduler: **HFSC** Queueing discipline to apply on the upload of this connection.

Setup connection speed and scheduler information for LAN interface #2

LAN interface: **DMZ** Interface of this connection.

LAN Scheduler: **HFSC** Queueing discipline to apply on the upload of this connection.

Next

7. The next page is specifically for shaping **VoIP traffic**, which we'll skip by clicking **Next**.

pfSense Traffic Shaper Wizard

Enable: ☐ This will raise the priority of VOIP traffic above all other traffic. Prioritize Voice over IP traffic

Next

VOIP specific settings

Provider: Generic (lowdelay) Choose Generic if your provider isn't listed.

Address: (Optional) If this is chosen, the provider field will be overridden. This allows you to just provide the IP address of the VOIP adaptor to prioritize. NOTE: You can also use a Firewall Alias in this location.

Download Speed: % The limit you want to apply.

Upload Speed: % The limit you want to apply.

Next

8. The next page, **PenaltyBox**, allows us to reduce the priority of a particular IP address or alias. This can be very useful, but we have no need for it at the moment and can skip it by clicking **Next**.

pfSense Traffic Shaper Wizard

Enable: ☐ This will lower the priority of traffic from this IP or alias. Penalize IP or Alias

Next

PenaltyBox specific settings

Address: This allows you to just provide the IP address of the computer(s) to penalize. NOTE: You can also use a Firewall Alias in this location.

Bandwidth: % The limit you want to apply.

Next

9. **Peer to Peer (P2P) Networking** can lower the priority and throttle all P2P traffic, or roughly 20 pre-defined popular P2P networks. We'll continue on by clicking **Next**:

pfSense Traffic Shaper Wizard	
Enable:	<input type="checkbox"/> This will lower the priority of P2P traffic below all other traffic. Please check the items that you would like to prioritize lower than normal traffic. Lower priority of Peer-to-Peer traffic
<input type="button" value="Next"/>	
p2p Catch all	
p2pCatchAll:	<input type="checkbox"/> When enabled, all uncategorized traffic is fed to the p2p queue.
Bandwidth:	<input type="text"/> % <input type="button" value="v"/> The limit you want to apply.
Enable/Disable specific P2P protocols	
Aimster:	<input type="checkbox"/> Aimster and other P2P using the Aimster protocol and ports
BitTorrent:	<input type="checkbox"/> Bittorrent and other P2P using the Torrent protocol and ports
BuddyShare:	<input type="checkbox"/> BuddyShare and other P2P using the BuddyShare protocol and ports

10. **Network Games** allows us to shape network gaming traffic. Roughly 20 popular gaming types are pre-defined. Click **Next** to continue:

pfSense Traffic Shaper Wizard	
Enable:	<input type="checkbox"/> This will raise the priority of gaming traffic to higher than most traffic. Prioritize network gaming traffic
<input type="button" value="Next"/>	
Enable/Disable specific games	
BattleNET:	<input type="checkbox"/> Battle.net - Virtually every game from Blizzard publishing should match this. This includes the following game series: Starcraft, Diablo, Warcraft. Guild Wars also uses this port.
Battlefield2:	<input type="checkbox"/> Battlefield 2 - this game uses a LARGE port range, be aware that you may need to manually rearrange the resulting rules to correctly prioritize other traffic.
CallOfDuty:	<input type="checkbox"/> Call Of Duty (United Offensive)
Counterstrike:	<input type="checkbox"/> Counterstrike - The ultimate 1st person shooter

11. The final page, **Other Applications**, allows us to shape other common types of traffic. Here we will click the checkbox to **Enable** other-application shaping and then set **MSRDP** to a **Higher priority**. Click **Next** to continue:

pfSense Traffic Shaper Wizard		
Enable:	<input checked="" type="checkbox"/>	This will help raise or lower the priority of other protocols higher than most traffic. Other networking protocols
<input type="button" value="Next"/>		
Remote Service / Terminal emulation		
MSRDP:	Higher priority ▼	Microsoft Remote Desktop Protocol
VNC:	Default priority ▼	Virtual Network Computing
AppleRemoteDesktop:	Default priority ▼	Apple Remote Desktop
PCAnywhere:	Default priority ▼	Symantec PC Anywhere
Messengers		
IRC:	Default priority ▼	Internet Relay Chat
Jabber:	Default priority ▼	Jabber instant messenger

12. Click **Finish** to apply the new settings:

<p>After pressing Finish the system will load the new profile. Please note that this may take a moment. Also note that the traffic shaper is stateful meaning that only new connections will be shaped. If this is an issue please reset the state table after loading the profile.</p>	
pfSense Traffic Shaper Wizard	
<input type="button" value="Finish"/>	

How it works...

Using the traffic-shaping wizard, we have defined a set of rules that will prioritize remote desktop traffic above all others. Even if the network is under heavy web, VoIP, or any other type of traffic, our remote desktop connections will perform well and be uninterrupted since they have been given priority.

Bridging interfaces

This recipe describes how to bridge together two interfaces in pfSense. Bridging allows you to join two networks together. For example, a network administrator may want to bridge a wired network with a wireless network.

How to do it...

1. Browse to **Interfaces** | **(assign)**.
2. Click the **Bridges** tab.
3. Click the "plus" button to create a new bridge.
4. Select the **Member Interfaces** with *Ctrl* + click.
5. Add a **Description**, such as **LAN DMZ Bridge**:

Firewall: Bridge: Edit

Bridge configuration

Member Interfaces WAN
LAN
DMZ
Interfaces participating in the bridge.

Description LAN DMZ Bridge

Show advanced options

Save Cancel

6. **Save** the changes:

Interfaces: Bridge

Interface assignments Interface Groups Wireless VLANs QinQs PPPs GRE GIF Bridges LAGG

Interface	Members	Description
BRIDGE0	LAN, DMZ	LAN DMZ Bridge

Note:
Here you can configure bridging of interfaces.

How it works...

Bridging combines two interfaces on the firewall into a single Layer-2 network. Our LAN and DMZ interfaces are now connected.

There's more...

Click the **Show advanced options** button to configure any of the following:

- ▶ RSTP/STP: Enable spanning tree options
 - ❑ Protocol
 - ❑ STP Interfaces
 - ❑ Valid time
 - ❑ Forward time
 - ❑ Hello time
 - ❑ Priority
 - ❑ Hold count
 - ❑ Interface priority
 - ❑ Path cost
- ▶ Cache size
- ▶ Cache entry expire time
- ▶ Span port
- ▶ Edge ports
- ▶ Auto Edge ports
- ▶ PTP ports
- ▶ Auto PTP ports
- ▶ Sticky ports
- ▶ Private ports

See also

- ▶ The *Identifying and assigning interfaces* recipe in *Chapter 1, Initial Configuration*

Creating a virtual LAN


This recipe describes how to create a virtual LAN in pfSense.

Getting ready

A VLAN allows a single physical switch to host multiple Layer-2 networks by separating ports with VLAN tags. A VLAN tag defines a separate virtual network. The pfSense firewall can attach to each VLAN by defining VLAN tags on the firewall interfaces.

How to do it...

1. Browse to **Interfaces | (assign)**.
2. Click the **VLANs** tab.
3. Click the "plus" button to add a new virtual LAN.
4. Select a **Parent Interface**. Refer to the interface assignment page as a reference (shown in the following screenshot). In this case, **DMZ** is assigned to interface **vr2** and we'll select that.



5. Specify a **VLAN tag**, any integer from 1 to 4094.
6. Add a **Description**, such as **My DMZ virtual LAN**.

Firewall: VLAN: Edit ?

VLAN configuration

Parent interface vr2 (00:0d:b9:1e:f6:9e) ▼
Only VLAN capable interfaces will be shown.

VLAN tag 99
802.1Q VLAN tag (between 1 and 4094)

Description My DMZ virtual LAN.
You may enter a description here for your reference (not parsed).

Save **Cancel**

7. **Save** the changes.

Interfaces: VLAN ?

Interface assignments **Interface Groups** **Wireless** **VLANs** **QinQs** **PPPs** **GRE** **GIF** **Bridges** **LAGG**

Interface	VLAN tag	Description
vr2	99	My DMZ virtual LAN.

Note:
Not all drivers/NICs support 802.1Q VLAN tagging properly. On cards that do not explicitly support it, VLAN tagging will still work, but the reduced MTU may cause problems. See the pfSense handbook for information on supported cards.

How it works...

Every packet destined for, or originating from our VLAN will be marked with the VLAN tag. This is how pfSense differentiates them from other network traffic and ensures they end up in the right place.

See also

- The *Identifying and assigning interfaces* recipe in *Chapter 1, Initial Configuration*

Creating a captive portal

This recipe describes how to create a captive portal with pfSense.

Getting ready

A **captive portal** is a web page that is displayed before a user is allowed to browse the web. This is most often seen at commercial Wi-Fi hotspots where you must pay for service before you are allowed to surf the web. In other scenarios, captive portals are used for authentication or end-user agreements.

During this recipe, we will configure pfSense to display an authentication captive portal before users are allowed to surf the web from our DMZ.

How to do it...

1. Browse to **Services | Captive Portal**.
2. From the **Captive portal** tab, click **Enable captive portal**.
3. Choose **Interfaces**; we'll select our DMZ as our interface.
4. Specify an **Idle timeout**; we'll say **10** minutes.
5. Specify a **Hard timeout**; we'll leave the default of **60** minutes.
6. Click **Enable logout popup window** so that users may log themselves out when they are finished.
7. Specify a **Redirection URL**, say **http://www.google.com**.

Services: Captive portal

Captive portal | Pass-through MAC | Allowed IP addresses | Vouchers | File Manager

☒ **Enable captive portal**

Interfaces

WAN
LAN
DMZ

Select the interface(s) to enable for captive portal.

Maximum concurrent connections

4 per client IP address (0 = no limit)

This setting limits the number of concurrent connections to the captive portal HTTP(S) server. This does not set how many users can be logged in to the captive portal, but rather how many users can load the portal page or authenticate at the same time! Default is 4 connections per client IP address, with a total maximum of 16 connections.

Idle timeout

10 minutes

Clients will be disconnected after this amount of inactivity. They may log in again immediately, though. Leave this field blank for no idle timeout.

Hard timeout

60 minutes

Clients will be disconnected after this amount of time, regardless of activity. They may log in again immediately, though. Leave this field blank for no hard timeout (not recommended unless an idle timeout is set).

Logout popup window

☒ **Enable logout popup window**


If enabled, a popup window will appear when clients are allowed through the captive portal. This allows clients to explicitly disconnect themselves before the idle or hard timeout occurs.

Redirection URL

http://www.google.com

If you provide a URL here, clients will be redirected to that URL instead of the one they initially tried to access after they've authenticated.


8. Select **Local User Manager** as the **Authentication**:



A dialog box titled "Authentication" with three radio button options. The "Local User Manager" option is selected, indicated by a red dot.

Authentication
<input type="radio"/> No Authentication
<input checked="" type="radio"/> Local User Manager
<input type="radio"/> RADIUS Authentication

9. **Save** the changes.
10. Browse to **System | User Manager**.
11. Click the **Users** tab.
12. Click the "plus" button to add a new user.
13. Enter a **Username**.
14. Enter and confirm a **Password**.
15. Enter a **Full name**:





The "System: User Manager" interface shows the "Users" tab selected. It contains a form for adding a new user with the following fields:

Field	Value
Defined by	USER
Disabled	<input type="checkbox"/>
Username	User1
Password (confirmation)
Full name	Captive portal user1 User's full name, for your own information only
Expiration date Leave blank if the account shouldn't expire, otherwise enter the expiration date in the following format: mm/dd/yyyy

16. **Save** the changes:

System: User Manager

Users Groups Settings Servers

Username	Full name	Disabled	Groups
 admin	System Administrator	<input type="checkbox"/>	admins
 User1	Captive portal user1	<input type="checkbox"/>	

Additional webConfigurator users can be added here. User permissions can be assigned directly or inherited from group memberships. An icon that appears grey indicates that it is a system defined object. Some system object properties can be modified but they cannot be deleted.

How it works...

By creating a captive portal on the DMZ as described, any user who attempts to browse the web will first have to authenticate on the following page. Once authenticated, they will be directed to Google, where they may surf the web before they encounter a timeout we have defined, at which point they will have to authenticate on the following page once again.

pfSense captive portal

Welcome to the pfSense Captive Portal! This is the default page since a custom page has not been defined.

Username:

Password:

There's more...

All three captive portal pages (login, logout and error) can be customized to fit your organization's styling. The easiest way to do this is to save each page as a file, edit it to your liking (without changing form, input IDs, or names), and then upload it using the options at the bottom of the **Captive Portal service** page.

Portal page contents	<div style="text-align: right;">Browse...</div> <p>Upload an HTML/PHP file for the portal page here (leave blank to keep the current one). Make sure to include a form (POST to "/>) with a submit button (name="accept") and a hidden field with name="redirurl" and value="". Include the "auth_user" and "auth_pass" and/or "auth_voucher" input fields if authentication is enabled, otherwise it will always fail. Example code for the form:</p> <pre><form method="post" action="/\$PORTAL_ACTION\$"> <input name="auth_user" type="text"> <input name="auth_pass" type="password"> <input name="auth_voucher" type="text"> <input name="redirurl" type="hidden" value="/\$PORTAL_REDIRURL\$"> <input name="accept" type="submit" value="Continue"> </form></pre>
Authentication error page contents	<div style="text-align: right;">Browse...</div> <p>The contents of the HTML/PHP file that you upload here are displayed when an authentication error occurs. You may include "\$PORTAL_MESSAGE\$", which will be replaced by the error or reply messages from the RADIUS server, if any.</p>
Logout page contents	<div style="text-align: right;">Browse...</div> <p>The contents of the HTML/PHP file that you upload here are displayed on authentication success when the logout popup is enabled.</p>
<div style="text-align: center;">Save</div> <p>Note: Changing any settings on this page will disconnect all clients! Don't forget to enable the DHCP server on your captive portal interface! Make sure that the default/maximum DHCP lease time is higher than the timeout entered on this page. Also, the DNS forwarder needs to be enabled for DNS lookups by unauthenticated clients to work.</p>	

6

Redundancy, Load Balancing, and Failover

In this chapter, we will cover:

- ▶ Configuring multiple WAN interfaces
- ▶ Configuring multi-WAN load balancing
- ▶ Configuring multi-WAN failover
- ▶ Configuring a web server load balancer
- ▶ Configuring a web server failover
- ▶ Configuring CARP firewall failover

Introduction

Redundancy, load-balancing, and failover are some of the most advanced features of modern networking. They are generally only necessary or required within large or sensitive systems and not all firewall and router products support these types of configurations. pfSense, of course, supports them all.

Redundant WAN interfaces (multi-WAN) provide a single firewall with multiple independent connections to the Internet. pfSense can then be configured to load-balance or failover the multi-WAN interfaces. Load-balancing would divide all traffic among the interfaces while failover would use a single interface, but upon failover it would automatically switch to another.

The pfSense load balancer allows for specific types of traffic (for example, web traffic) to be distributed among multiple servers. The ability to create your own webfarm is built right into pfSense!

Redundant firewalls allow the system to survive the death of a physical firewall machine. Using a CARP configuration, pfSense can be configured to failover to a backup firewall in case the primary dies.

Configuring multiple WAN interfaces

This recipe describes how to configure multiple WAN interfaces in pfSense.

Getting ready

A pfSense system with a single WAN interface is nearly plug-and-play since a default gateway is created automatically. However, some of the recipes in this chapter require multiple WAN connections and those gateways must be configured manually. The following recipe describes how to configure two WAN interfaces which can be used later for redundant load balancing and/or failover.



The following interfaces will be configured with private IP addresses for the purpose of this example, but an actual configuration would require each WAN interface to be properly configured using the settings provided by their respective ISPs.

How to do it...

1. Browse to **System | Routing**.
2. Select the **Gateways** tab.
3. Take note that the gateway for our existing WAN interface was created automatically, set as **default**, and usually set as **dynamic**:

System: Gateways

Gateways Routes Groups

Name	Interface	Gateway	Monitor IP	Description
GW_WAN (default)	WAN	dynamic	dynamic	Interface wan Dynamic Gateway

4. Click the "plus" button to add a new gateway.
5. Choose the **Interface** for our existing WAN connection.
6. Specify a **Name** for the gateway.
7. Specify the **Gateway** IP address.
8. Check **Default Gateway**.
9. Add a **Description**, such as **WAN Gateway**:

System: Gateways: Edit gateway S ?

Edit gateway

Interface	WAN ▾ Choose which interface this gateway applies to.
Name	WANGateway Gateway name
Gateway	172.16.1.1 Gateway IP address
Default Gateway	<input checked="" type="checkbox"/> Default Gateway This will select the above gateway as the default gateway
Monitor IP	<input type="text" value="172.16.1.1"/> Alternative monitor IP Enter an alternative address here to be used to monitor the link. This is used for the quality RRD graphs as well as the load balancer entries. Use this if the gateway does not respond to ICMP echo requests (pings).
Advanced	<input type="button" value="Advanced"/> - Show advanced option
Description	WAN Gateway You may enter a description here for your reference (not parsed).

10. **Save** the changes:

System: Gateways S ?

Gateways **Routes** **Groups**

Name	Interface	Gateway	Monitor IP	Description
GW_WAN	WAN	dynamic	172.16.1.1	Interface wan Dynamic Gateway
WANGateway (default)	WAN	172.16.1.1	172.16.1.1	WAN Gateway

11. Click the "plus" button to add a new gateway.
12. Choose the **Interface** for our new WAN connection.
13. Specify a **Name** for the gateway.
14. Specify the **Gateway** IP address.
15. Add a **Description**, such as **WAN2 gateway**:

System: Gateways: Edit gateway

Edit gateway

Interface

WAN2

Choose which interface this gateway applies to.

Name

WAN2Gateway

Gateway name

Gateway

172.16.2.1

Gateway IP address

Default Gateway

☐
Default Gateway

This will select the above gateway as the default gateway

Monitor IP

172.16.2.1

Alternative monitor IP

Enter an alternative address here to be used to monitor the link. This is used for the quality RRD graphs as well as the load balancer entries. Use this if the gateway does not respond to ICMP echo requests (pings).

Advanced

Advanced

- Show advanced option

Description

WAN2 Gateway

You may enter a description here for your reference (not parsed).

Save

Cancel

16. **Save** the changes.
17. **Apply** changes, if necessary.

System: Gateways

Gateways

Routes

Groups

Name	Interface	Gateway	Monitor IP	Description
GW_WAN	WAN	dynamic	172.16.1.1	Interface wan Dynamic Gateway
WANGateway (default)	WAN	172.16.1.1	172.16.1.1	WAN Gateway
WAN2Gateway	WAN2	172.16.2.1	172.16.2.1	WAN2 Gateway

18. Browse to **Interfaces** | **WAN**.

19. Choose **Static** as the **Type**:

General configuration	
Enable	<input checked="" type="checkbox"/> Enable Interface
Description	<input type="text" value="WAN"/> Enter a description (name) for the interface here.
Type	Static ▾

20. Specify an **IP Address**.

21. Select our newly created **Gateway**.

22. Check **Block private networks**.

23. Check **Block bogon networks**:

Static IP configuration	
IP address	<input type="text" value="172.16.1.2"/> / 24 ▾
Gateway	WANGateway - 172.16.1.1 ▾ If this interface is an Internet connection, select an existing Gateway from the list or add a new one.
Private networks	
<input checked="" type="checkbox"/> Block private networks When set, this option blocks traffic from IP addresses that are reserved for private networks as per RFC 1918 (10/8, 172.16/12, 192.168/16) as well as loopback addresses (127/8). You should generally leave this option turned on, unless your WAN network lies in such a private address space, too.	
<input checked="" type="checkbox"/> Block bogon networks When set, this option blocks traffic from IP addresses that are reserved (but not RFC 1918) or not yet assigned by IANA. Bogons are prefixes that should never appear in the Internet routing table, and obviously should not appear as the source address in any packets you receive.	
Save Cancel	

24. **Save** the changes.

25. Browse to **Interfaces** | **WAN2**.

26. Choose **Static** as the **Type**:

General configuration	
Enable	<input checked="" type="checkbox"/> Enable Interface
Description	<input type="text" value="WAN2"/> Enter a description (name) for the interface here.
Type	Static ▾

27. Specify an **IP Address**.
28. Select our newly created **Gateway**.
29. Check **Block private networks**.
30. Check **Block bogon networks**:

The screenshot shows the pfSense configuration interface. The top section is titled "Static IP configuration" and contains two fields: "IP address" set to "172.16.2.2" and "Gateway" set to "WAN2Gateway - 172.16.2.1". Below these fields is a note: "If this interface is an Internet connection, select an existing Gateway from the list or add a new one." The bottom section is titled "Private networks" and contains two checked options: "Block private networks" and "Block bogon networks". Each option has a descriptive text block explaining its function. At the bottom of the form are "Save" and "Cancel" buttons.

31. **Save** the changes.
32. **Apply** changes, if necessary.

How it works...

Only the first WAN interface created in pfSense will create an automatically generated default gateway. By creating a manual gateway for our new WAN interface, as we've just done, we can now properly configure that interface for the available redundancy features described throughout the rest of this chapter.

There's more...

Remember to block private and bogon networks for WAN interfaces in public network ranges.

See also

- ▶ The *Configuring interfaces* recipe in *Chapter 1, Initial Configuration*
- ▶ The *Creating a gateway* recipe in *Chapter 5, Advanced Configuration*
- ▶ The *Configuring multi-WAN load balancing* recipe
- ▶ The *Configuring multi-WAN failover* recipe

Configuring multi-WAN load balancing

This recipe describes how to configure multi-WAN load balancing on a single pfSense system.

Getting ready

Throughout this recipe, we will configure load-balancing for two separate WAN interfaces. Make sure that the WAN interfaces are first properly configured; refer to the previous recipe for the specifics.



Every time multi-WAN load balancing is in effect, failover is as well. If we wanted to enable multi-WAN failover only, we would refer to the next recipe.

How to do it...

1. Browse to **System | Routing**.
2. Select the **Groups** tab.
3. Enter a **Group Name**.
4. Set the **Gateway Priority** of both our WAN gateways to **Tier 1**.
5. Leave the **Trigger Level** set to **Member Down**.
6. Add a **Description**:

System: Gateways: Edit gateway	
Edit gateway entry	
Group Name	<input type="text" value="LoadBalancedGroup"/> Group Name
Gateway Priority	<div> <div>Never</div> <div>Tier 1</div> <div>Tier 1</div> </div> <div> GW_WAN - Interface wan Dynamic Gateway WANGateway - WAN Gateway WAN2Gateway - WAN2 Gateway </div> <p>Link Priority The priority selected here defines in what order failover and balancing of links will be done. Multiple links of the same priority will balance connections until all links in the priority will be exhausted. If all links in a priority level are exhausted we will use the next available link(s) in the next priority level.</p>
Trigger Level	<div>Member Down</div> When to trigger exclusion of a member
Description	<input type="text" value="Round-robin effect for gateways on the same tier."/> You may enter a description here for your reference (not parsed).
<div>Save</div> <div>Cancel</div>	

7. **Save** the changes.
8. **Apply** changes, if necessary:

System: Gateway Groups

Gateways Routes **Groups**

Group Name	Gateways	Priority	Description
LoadBalancedGroup	WANGATEWAY WAN2GATEWAY	Tier 1 Tier 1	Round-robin effect for gateways on the same tier.

9. Browse to **System | Routing**.
10. Edit our WAN gateway.
11. Specify an external IP address that responds to pings in the **Monitor IP** field. I have chosen the IP for `http://www.google.com/` in this example, but you may prefer to choose an address closer to your firewall for the sake of performance (an IP within your ISP network perhaps).
12. **Save** the changes.
13. Edit our WAN2 gateway.
14. Specify an external IP address that responds to pings in the **Monitor IP** field. I have chosen the IP for `http://www.yahoo.com/` in this example.
15. **Save** the changes.
16. **Apply** changes, if necessary:

System: Gateways

Gateways **Routes** Groups

Name	Interface	Gateway	Monitor IP	Description
GW_WAN	WAN	dynamic	172.16.1.1	Interface wan Dynamic Gateway
WANGateway (default)	WAN	172.16.1.1	173.194.33.104	WAN Gateway
WAN2Gateway	WAN2	172.16.2.1	98.137.149.56	WAN2 Gateway

17. Browse to **Firewall | Rules**.
18. Click the "plus" button to create a new firewall rule.
19. Select the **pass** action.

20. Ensure the LAN interface is selected.
21. Set the **Protocol** to **any**.
22. Set the **Source** to **LAN subnet**.
23. Set the **Destination** to **any**.
24. Add a **Description**.
25. In **Advanced Features**, under **Gateway**, click the **Advanced** button to show advanced gateway features.
26. Set **Gateway** to **LoadBalancedGroup**.
27. **Save** the changes.
28. **Apply** changes, if necessary.

Firewall: Rules S L ?

Floating **WAN** **LAN** **WAN2**

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description	
1	*	LAN net	*	*	*	LoadBalancedGroup	none		Load balance all of our traffic.	

☒ pass
☐ pass (disabled)
 ☒ block
☐ block (disabled)
 ☒ reject
☐ reject (disabled)
 ☒ log
☐ log (disabled)

Hint:

Rules are evaluated on a first-match basis (i.e. the action of the first rule to match a packet will be executed). This means that if you use block rules, you'll have to pay attention to the rule order. Everything that isn't explicitly passed is blocked by default.

You may drag and drop rules using your mouse to reorder the rule ordering.

How it works...

All traffic from our LAN will pass through our gateway group. Since our gateway group consists of our two WAN gateways on the same level of priority, they will alternate back and forth in a round-robin type style.

Also, by monitoring external IP addresses on each gateway, pfSense will know when a gateway is down and exclude that member from the group. Every time load-balancing is used, failover is also in effect by default.

There's more...

We've defined our gateway group to trigger on **Member Down**, but there are several other options:

- ▶ **Member Down:** Triggered when the **Monitor IP** defined in the gateway's settings stops responding to ICMP pings
- ▶ **Packet Loss:** Triggered when packets traveling through this gateway are lost
- ▶ **High Latency:** Triggered when packets traveling through this gateway experience high latency
- ▶ **Packet Loss or High Latency:** Triggered when packets traveling through this gateway are lost or experience high latency

See also

- ▶ The *Configuring multiple WAN interfaces* recipe

Configuring multi-WAN failover



This recipe describes how to configure multi-WAN failover on a single pfSense system.

Getting ready



Throughout this recipe, we will configure failover for our two separate WAN interfaces. Make sure that the WAN interfaces are first properly configured; refer to the previous recipe for the specifics.

How to do it...

1. Browse to **System | Routing**.
2. Select the **Groups** tab.
3. Enter a **Group Name**.
4. Set the **Gateway Priority** of our WAN gateway to **Tier 1**.
5. Set the **Gateway Priority** of our WAN2 gateway to **Tier 2**.
6. Leave the **Trigger Level** set to **Member Down**.
7. Add a **Description**:



System: Gateways: Edit gateway  

Edit gateway entry

Group Name	 FailoverGroup Group Name
Gateway Priority	<div> <div>Never ▼</div> <div>Tier 1 ▼</div> <div>Tier 2 ▼</div> </div> <div> GW_WAN - Interface wan Dynamic Gateway WANGateway - WAN Gateway WAN2Gateway - WAN2 Gateway </div> <p>Link Priority The priority selected here defines in what order failover and balancing of links will be done. Multiple links of the same priority will balance connections until all links in the priority will be exhausted. If all links in a priority level are exhausted we will use the next available link(s) in the next priority level.</p>
Trigger Level	<div>Member Down ▼</div> <p>When to trigger exclusion of a member</p>
Description	 Failover for WAN down. You may enter a description here for your reference (not parsed).





Save **Cancel**

8. **Save** the changes.
9. **Apply** changes, if necessary:

System: Gateway Groups  

Gateways **Routes** **Groups**

Group Name	Gateways	Priority	Description
FailoverGroup	WANGATEWAY WAN2GATEWAY	Tier 1 Tier 2	Failover for WAN down.

10. Browse to **System | Routing**.
11. **Edit** our WAN gateway.
12. Specify an external IP address that responds to pings in the **Monitor IP** field. I chose the IP for google.com in this example.
13. **Save** the changes.
14. **Edit** our WAN2 gateway.
15. Specify an external IP address that responds to pings in the **Monitor IP** field. I chose the IP for yahoo.com in this example.
16. **Save** the changes.

17. **Apply** changes, if necessary:

System: Gateways S ?

Gateways Routes Groups

Name	Interface	Gateway	Monitor IP	Description
GW_WAN	WAN	dynamic	172.16.1.1	Interface wan Dynamic Gateway
WANGateway (default)	WAN	172.16.1.1	173.194.33.104	WAN Gateway
WAN2Gateway	WAN2	172.16.2.1	98.137.149.56	WAN2 Gateway

18. Browse to **Firewall | Rules**.

19. Click the "plus" button to create a new firewall rule.

20. Select the **Pass Action**.

21. Ensure the LAN interface is selected.

22. Set the **Protocol** to **any**.

23. Set the **Source** to **LAN subnet**.

24. Set the **Destination** to **any**.

25. Add a **Description**.

26. In **Advanced Features**, under **Gateway**, click the **Advanced** button to show advanced gateway features.

27. Set **Gateway** to **FailoverGroup**.

28. **Save** the changes.

29. **Apply** the changes:

Firewall: Rules

Floating
WAN
LAN
WAN2

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description
1	*	LAN net	*	*	*	FailoverGroup	none		Failover for WAN down.

pass pass (disabled)
block block (disabled)
reject reject (disabled)
log log (disabled)

Hint:

Rules are evaluated on a first-match basis (i.e. the action of the first rule to match a packet will be executed). This means that if you use block rules, you'll have to pay attention to the rule order. Everything that isn't explicitly passed is blocked by default.

You may drag and drop rules using your mouse to reorder the rule ordering.

How it works...

All traffic from our LAN will pass through our gateway group. Since our gateway group consists of two WAN gateways on separate priority levels, our backup gateway (**Tier 2**) will kick into place when our primary gateway (**Tier 1**) goes down.

There's more...

We've defined our gateway group to trigger on **Member Down**, but there are several other options:

- ▶ **Member Down:** Triggered when the Monitor IP defined in the gateway's settings stops responding to ICMP pings
- ▶ **Packet Loss:** Triggered when packets traveling through this gateway are lost
- ▶ **High Latency:** Triggered when packets traveling through this gateway experience high latency
- ▶ **Packet Loss or High Latency:** Triggered when packets traveling through this gateway are lost or experience high latency

See also

- ▶ The *Configuring multiple WAN interfaces* recipe
- ▶ The *Configuring multi-WAN load balancing* recipe

Configuring a web server load balancer

This recipe describes how to configure a small webfarm using the pfSense load balancer.

Getting ready

The load balancer allows pfSense to distribute certain types of traffic to multiple machines. A common use of this feature is to distribute incoming HTTP requests to multiple web servers and the following recipe describes how the load balancer can create a webfarm to accomplish this.

How to do it...

1. Browse to **Services | Load Balancer**.
2. Click the **Monitor** tab.
3. Click the "plus" button to add a new monitor.
4. Specify a **Name**.
5. Add a **Description**.
6. Set **Type** to **HTTP**.
7. Set **Host** to an unused IP address that you will later use as the IP address for the virtual server. The virtual server will be configured to pass requests to the actual servers in the webfarm; so we will monitor this IP address.
8. Leave **HTTP Code** set to **200 OK**.

Services: Load Balancer: Monitor: Edit

Edit Load Balancer - Monitor entry

Name	WebfarmMonitor
Description	Monitor the webfarm pool.
Type	HTTP
HTTP	<div>Path: /</div> <div>Host: 192.168.1.200 Hostname for Host: header if needed.</div> <div>HTTP Code: 200 OK</div>

Save Cancel

9. **Save** the changes.
10. **Apply** changes, if necessary:

Services: Load Balancer: Monitor S L ?

Pools **Virtual Servers** **Monitors**

Name	Type	Description
WebfarmMonitor	http	Monitor the webfarm pool.

11. Click the **Pools** tab.
12. Click the "plus" button to add a new pool.
13. Specify a **Name**.
14. Set the **Mode** to **Load Balance**.
15. Add a **Description**.
16. Set the **Port** to **80** (since we're creating a webserver load balancer).
17. Set **Monitor** to our newly created **WebfarmMonitor**.
18. Specify the **Server IP Address** of each webserver in the farm and click **Add to pool**:

Services: Load Balancer: Pool: Edit S L ?

Add/edit Load Balancer - Pool entry

Name WebfarmPool

Mode Load Balance

Description Webfarm pool for www.mydomain.com

Port 80
This is the port your servers are listening on.

Add Item to pool

Monitor WebfarmMonitor

Server IP Address **Add to pool**

Current Pool Members

Members	Pool Disabled	Enabled (default)
	<input type="text"/> <input type="button" value="Remove"/>	<input type="text" value="192.168.1.201"/> <input type="text" value="192.168.1.202"/> <input type="button" value="Remove"/>

Save **Cancel**

19. **Save** the changes.
20. **Apply** changes, if necessary:

Services: Load Balancer: Pool S L ?

Pools **Virtual Servers** **Monitors**

Name	Mode	Servers	Port	Monitor	Description
WebfarmPool	loadbalance	192.168.1.201 192.168.1.202	80	WebfarmMonitor	Webfarm pool for www.mydomain.com

21. Click the **Virtual Servers** tab.
22. Click the "plus" button to add a new virtual server.
23. Specify a **Name**.
24. Add a **Description**.
25. Set the **IP Address** to the same IP address we chose for our newly created **WebfarmMonitor**.
26. Set **Port** to **80** (since we're dealing with a webserver load balancer).
27. Set **Virtual Server Pool** to our newly created **WebfarmPool**:

Services: Load Balancer: Virtual Server: Edit S L ?

Edit Load Balancer - Virtual Server entry

Name

Description

IP Address
This is normally the WAN IP address that you would like the server to listen on. All connections to this IP and port will be forwarded to the pool cluster.

Port
This is the port that the clients will connect to. All connections to this port will be forwarded to the pool cluster.

Virtual Server Pool

Fall Back Pool
NOTE: This is the server that clients will be redirected to if *ALL* servers in the pool are offline.

Note: Don't forget to add a firewall rule for the virtual server/pool after you're finished setting it up.

28. **Submit** the changes.
29. **Apply** changes, if necessary.

Services: Load Balancer: Virtual Servers						
<div> Pools Virtual Servers Monitors </div>						
Name	Mode	IP Address	Port	Pool	Fall Back Pool	Description
WebfarmVirtualServer	redirect_mode	192.168.1.200	80	WebfarmPool	none	Virtual webserver for www.mydomain.com

How it works...

Throughout this recipe, we've configured pfSense to divide incoming HTTP (port 80) traffic among two separate web servers. Our pool defines the location of the web servers and the load balance mode (as opposed to failover). Our virtual server defines the IP address we will use in our NAT and firewall rules to listen for the HTTP requests, which the virtual server will know to distribute equally to all the servers defined in our pool. The monitor will check the status of the pool by periodically making a web request. Since the request is directed to the virtual server's IP address, it will take the pool offline if any of the servers in the farm doesn't respond with a **200 OK** status. Since this is the case, we may want to define a failover pool as well.

There's more

Sticky connections can be used to ensure that the client will always make requests to the same server during a given length of time. If the next request is made after the "sticky connection timeout" length, then that request could be handled by any server in the farm.

Developers often need this feature to ensure the integrity of webserver specific data (in-memory cache), but it is not as reliable as using shared session storage.

See also

- ▶ The *Creating a NAT port forward rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Creating a firewall rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Configuring a web server failover* recipe

Configuring a web server failover

This recipe describes how to configure a small webfarm using the pfSense load balancer.

Getting ready

The load balancer also allows pfSense to send traffic to a failover server in case of downtime. In the following recipe, we will configure a backup webserver to take place of the primary in the event of downtime.

How to do it...

1. Browse to **Services | Load Balancer**.
2. Click the **Monitor** tab.
3. Click the "plus" button to add a new monitor.
4. Specify a **Name**.
5. Add a **Description**.
6. Set **Type** to **HTTP**.
7. Set **Host** to the IP address of our primary webserver.
8. Leave **HTTP Code** set to **200 OK**:

Services: Load Balancer: Monitor: Edit S L ?

Edit Load Balancer - Monitor entry

Name	WebserverMonitor
Description	Monitor the primary webserver.
Type	HTTP ▼
HTTP	<div>Path <input type="text" value="/"/></div> <div>Host <input type="text" value="192.168.1.201"/> <small>Hostname for Host: header if needed.</small></div> <div>HTTP Code <input type="text" value="200 OK"/> ▼</div>

Save **Cancel**

9. **Save** the changes.
10. **Apply** changes, if necessary:

Services: Load Balancer: Monitor S L ?

Pools **Virtual Servers** **Monitors**

Name	Type	Description
WebserverMonitor	http	Monitor the primary webserver.

11. Click the **Pools** tab.
12. Click the "plus" button to add a new pool.
13. Specify a **Name**.
14. Set the **Mode** to **Manual Failover**.
15. Add a **Description**.
16. Set the **Port** to **80** (since we're creating a webserver failover).
17. Set **Monitor** to our newly created **WebFailoverMonitor**.
18. Specify the **Server IP Address** of the primary webserver and click **Add to pool**. The IP address will appear in the **Enabled (default)** list.
19. Specify the **Server IP Address** of the backup webserver and click **Add to pool**. The IP address will appear in the **Pool Disabled** list:

Services: Load Balancer: Pool: Edit S L ?

Add/edit Load Balancer - Pool entry

Name

Mode

Description

Port
This is the port your servers are listening on.

Add item to pool

Monitor

Server IP Address

Current Pool Members

Members	Pool Disabled	Enabled (default)
	<input type="text" value="192.168.1.202"/> <input type="button" value="Remove"/>	<input type="text" value="192.168.1.201"/> <input type="button" value="Remove"/>

20. **Save** the changes.
21. **Apply** changes, if necessary:

Services: Load Balancer: Pool S L ?

Pools **Virtual Servers** **Monitors**

Name	Mode	Servers	Port	Monitor	Description
WebFailoverPool	failover	192.168.1.201	80	WebserverMonitor	Web failover pool for www.mydomain.com

22. Click the **Virtual Servers** tab.
23. Click the "plus" button to add a new virtual server.
24. Specify a **Name**.
25. Add a **Description**.
26. Set the **IP Address** to an unused IP address.
27. Set **Port** to **80** (since we're dealing with a webserver failover).
28. Set **Virtual Server Pool** to our newly created **WebFailoverPool**:

Services: Load Balancer: Virtual Server: Edit S L ?

Edit Load Balancer - Virtual Server entry

Name	WebVirtualServer
Description	Virtual webserver for www.mydomain.com
IP Address	192.168.1.200 <small>This is normally the WAN IP address that you would like the server to listen on. All connections to this IP and port will be forwarded to the pool cluster.</small>
Port	80 <small>This is the port that the clients will connect to. All connections to this port will be forwarded to the pool cluster.</small>
Virtual Server Pool	WebFailoverPool ▼
Fall Back Pool	none ▼ NOTE: This is the server that clients will be redirected to if *ALL* servers in the pool are offline.

Note: Don't forget to add a firewall rule for the virtual server/pool after you're finished setting it up.

29. **Submit** the changes.
30. **Apply** changes, if necessary:

Services: Load Balancer: Virtual Servers S L ?

Pools **Virtual Servers** **Monitors**

Name	Mode	IP Address	Port	Pool	Fall Back Pool	Description
WebVirtualServer	redirect_mode	192.168.1.200	80	WebFailoverPool	none	Virtual webserver for www.mydomain.com

How it works...

Throughout this recipe, we've configured pfSense to automatically redirect traffic from the primary webserver to the backup webserver in the event of a failure. Our pool defines the location of the webserver and the failover mode (as opposed to load balance). Our virtual server defines the IP address we will use in our NAT and firewall rules to listen for the HTTP requests, which the virtual server redirects to the pool we've defined. The monitor will check on the status of the primary webserver by periodically making a web request. If the response coming back is **200 OK**, then the pool will send traffic to the primary server; otherwise, it will send traffic to the backup server.

See also

- ▶ The *Creating a NAT port forward rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Creating a firewall rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Configuring a web server load balancer* recipe

Configuring CARP firewall failover

This recipe describes how to configure two pfSense firewalls for failover.

Getting ready

Hardware redundancy requires additional hardware, of course. To configure a firewall failover, we will need two separate and identical pfSense machines. We also want each machine to have an additional interface dedicated to the syncing process (which we'll refer to as **pfsync**). The example in this recipe will utilize two separate pfSense firewall appliances, each with three interfaces (WAN, LAN, and pfsync).



The following interfaces will be configured with private IP addresses for the purposes of this example, but an actual configuration would require each WAN interface to be properly configured using the settings provided by their respective ISPs.

How to do it...


1. Configure the interfaces of our first machine, **primary-pfsense**, as follows:
 - ❑ **WAN:** 192.168.111.2
 - ❑ **SYNC:** 192.168.222.2
 - ❑ **LAN:** 192.168.1.2
2. Configure the interfaces of our second machine, **backup-pfsense**, as follows:
 - ❑ **WAN:** 192.168.111.3
 - ❑ **SYNC:** 192.168.222.3
 - ❑ **LAN:** 192.168.1.3
3. On both machines, add a firewall to allow all traffic on the SYNC interface:
 1. Browse to **Firewall | Rules**.
 2. Click the **SYNC Interface** tab.
 3. Click the "plus" button to add a new firewall rule.
 4. Set **Protocol** to **any**.

Firewall: Rules: Edit
S L ?

Edit Firewall rule

Action	<div>Pass ▾</div> <p>Choose what to do with packets that match the criteria specified below. Hint: the difference between block and reject is that with reject, a packet (TCP RST or ICMP port unreachable for UDP) is returned to the sender, whereas with block the packet is dropped silently. In either case, the original packet is discarded.</p>
Disabled	<input type="checkbox"/> Disable this rule Set this option to disable this rule without removing it from the list.
Interface	<div>SYNC ▾</div> <p>Choose on which interface packets must come in to match this rule.</p>
Protocol	<div>any ▾</div> <p>Choose which IP protocol this rule should match. Hint: in most cases, you should specify <i>TCP</i> here.</p>


4. Add a **Description**:









Description	 Allow all traffic on SYNC interface. You may enter a description here for your reference.
<div>Save Cancel</div>	

5. **Save** the changes.
6. **Apply** changes, if necessary.

Firewall: Rules S L ?

Floating WAN LAN **SYNC**

ID	Proto	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description
	*	*	*	*	*	*	none		Allow all traffic on SYNC interface.

 pass
 pass (disabled)
  block
 block (disabled)
  reject
 reject (disabled)
  log
 log (disabled)

Hint:

Rules are evaluated on a first-match basis (i.e. the action of the first rule to match a packet will be executed). This means that if you use block rules, you'll have to pay attention to the rule order. Everything that isn't explicitly passed is blocked by default.

You may drag and drop rules using your mouse to reorder the rule ordering.

7. On the backup-pfsense machine, we need to enable CARP synchronization and configure it as a backup only:
 1. Browse to **Firewall | Virtual IPs**.
 2. Click the **CARP Settings** tab.
 3. Check **Synchronize Enabled**.
 4. Set **Synchronize Interface** to **SYNC**.

Services: CARP Settings: Edit ?

Virtual IPs **CARP Settings**

Synchronize Enabled ☒

PFSync transfers state insertion, update, and deletion messages between firewalls. Each firewall sends these messages out via multicast on a specified interface, using the PFSYNC protocol (IP Protocol 240). It also listens on that interface for similar messages from other firewalls, and imports them into the local state table.

NOTE: Clicking save will force a configuration sync!

Synchronize Interface **SYNC**

If Synchronize State is enabled, it will utilize this interface for communication.

NOTE: We recommend setting this to a interface other than LAN! A dedicated interface works the best.

NOTE: You must define a IP on each machine participating in this failover group.

NOTE: You must have an IP assigned to the interface on any participating sync nodes.

8. **Save** the changes.
9. We have now finished configuring the backup firewall.
10. On the primary-pfsense machine, we need to enable CARP synchronization and configure it to act as the primary firewall:
 1. Browse to **Firewall | Virtual IPs**.
 2. Click the **CARP Settings** tab.
 3. Check **Synchronize Enabled**.
 4. Set **Synchronize Interface** to **SYNC**.

Services: CARP Settings: Edit

Virtual IPs **CARP Settings**

Synchronize Enabled☒

PFSync transfers state insertion, update, and deletion messages between firewalls. Each firewall sends these messages out via multicast on a specified interface, using the PFSYNC protocol (IP Protocol 240). It also listens on that interface for similar messages from other firewalls, and imports them into the local state table.
NOTE: Clicking save will force a configuration sync!

Synchronize Interface

SYNC ▾

If Synchronize State is enabled, it will utilize this interface for communication.
NOTE: We recommend setting this to a interface other than LAN! A dedicated interface works the best.
NOTE: You must define a IP on each machine participating in this failover group.
NOTE: You must have an IP assigned to the interface on any participating sync nodes.

11. Check **Synchronize rules**:

Synchronize rules☒

When this option is enabled, this system will automatically sync the firewall rules to the other CARP host when changes are made..

12. Check **Synchronize nat**:

Synchronize nat☒



When this option is enabled, this system will automatically sync the NAT rules over to the other CARP host when changes are made.

13. Check **Synchronize Virtual IPs**:

Synchronize Virtual IPs☒

When this option is enabled, this system will automatically sync the CARP Virtual IPs to the other CARP host when changes are made.


14. Set **Synchronize to IP** to the IP address of backup-pfsense.
15. Set **Remote System Password** to the password of backup-pfsense:

Synchronize to IP	 192.168.222.3 Enter the IP address of the firewall you are synchronizing with.
Remote System Password	 Enter the webConfigurator password of the system that you would like to synchronize with.
<div>Save Cancel</div>	


16. **Save** the changes.

17. We must now configure a virtual IP address for the WAN interface on the primary-pfsense machine:

1. Browse to **Firewall | Virtual IPs**.
2. Click the **Virtual IPs** tab.
3. Click the "plus" **button** to add a new virtual IP.
4. Set the **Type** to **CARP**.
5. Set the **Interface** to **WAN**.
6. Set the **IP Address** to the single WAN address that will be used throughout your systems, regardless of whether the primary or backup firewall is in effect.
7. Create a **Virtual IP Password**.
8. Leave the **VHID Group** set to **1**.
9. Leave the **Advertising Frequency** at **0**.
10. Add a **Description**.

Firewall: Virtual IP Address: Edit	
Edit Virtual IP	
Type	<input type="radio"/> Proxy ARP <input checked="" type="radio"/> CARP <input type="radio"/> Other <input type="radio"/> IP Alias
Interface	WAN
IP Address(es)	Type: Network Address:  192.168.111.1 / 24 This must be the network's subnet mask. It does not specify a CIDR range.
Virtual IP Password Enter the VHID group password.
VHID Group	1 Enter the VHID group that the machines will share
Advertising Frequency	0 The frequency that this machine will advertise. 0 = master. Anything above 0 designates a backup.
Description	 WAN VIP for our CARP configuration. You may enter a description here for your reference (not parsed).
<div>Save Cancel</div>	

11. **Save** the changes.
12. **Apply** changes, if necessary.



18. On the primary-pfsense machine we must now configure a virtual IP address for the LAN interface.
 1. Browse to **Firewall | Virtual IPs**.
 2. Click the **Virtual IPs** tab.
 3. Click the "plus" **button** to add a new virtual IP.
 4. Set the **Type** to **CARP**.
 5. Set the **Interface** to **LAN**.
 6. Set the **IP Address** to the single LAN address that will be used as the default gateway for all of our clients, regardless of whether the primary or backup firewall is in effect.
 7. Create a **Virtual IP Password**.
 8. Leave the **VHID Group** set to **2**.
 9. Leave the **Advertising Frequency** at **0**.
 10. Add a **Description**.

Firewall: Virtual IP Address: Edit

Edit Virtual IP

Type ☐ Proxy ARP ☒ CARP ☐ Other ☐ IP Alias

Interface LAN ▼

IP Address(es)
 Type: Network
 Address: 192.168.1.1 / 24 ▼ *This must be the network's subnet mask. It does not specify a CIDR range.*

Virtual IP Password
 Enter the VHID group password.

VHID Group
 2 ▼
 Enter the VHID group that the machines will share.

Advertising Frequency
 0 ▼
 The frequency that this machine will advertise. 0 = master. Anything above 0 designates a backup.

Description
 LAN VIP for our CARP configuration.
 You may enter a description here for your reference (not parsed).

Save Cancel

11. **Save** the changes.
12. **Apply** changes, if necessary.

Firewall: Virtual IP Addresses

Virtual IPs **CARP Settings**

Virtual IP address	Type	Description
192.168.111.1/24 (vhid 1)	CARP	WAN VIP for our CARP configuration.
192.168.1.1/24 (vhid 2)	CARP	LAN VIP for our CARP configuration.

Note:
 The virtual IP addresses defined on this page may be used in NAT mappings.
 You can check the status of your CARP Virtual IPs and interfaces here.

How it works...

This recipe has described how to create a failover firewall using CARP. The two firewalls constantly sync their rules, NAT, and virtual IP settings so that if the primary dies, the backup will seamlessly take its place.

The trick to synchronization is the advertising frequency set within each virtual IP. The primary server has an advertising frequency set to **0**, but when the settings are synchronized, the advertising frequency is incremented for the backup server (that is, the backup server's advertising frequency is set to **1**). That is how pfSense distinguishes the machines and synchronization settings.

See also

- ▶ The *Creating a NAT port forward rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Creating a firewall rule* recipe in *Chapter 3, General Configuration*
- ▶ The *Creating a virtual IP* recipe in *Chapter 5, Advanced Configuration*

7

Services and Maintenance

In this chapter, we will cover:

- ▶ Enabling OLSR
- ▶ Enabling PPPoE
- ▶ Enabling RIP
- ▶ Enabling SNMP
- ▶ Enabling UPnP and NAT-PMP
- ▶ Enabling OpenNTPD
- ▶ Enabling **Wake On LAN (WOL)**
- ▶ Enabling SIPROXD
- ▶ Enabling external logging (syslog server)
- ▶ Using ping
- ▶ Using traceroute
- ▶ Backing up the configuration file
- ▶ Restoring the configuration file
- ▶ Configuring automatic configuration file backup
- ▶ Updating pfSense firmware

Introduction

pfSense offers a myriad of modern networking services and features. This chapter lays out the most commonly used services and maintenance features by describing what they do and how to use them.

The recipes in the first half of the chapter describe how to enable the most popular networking services in pfSense—everything from SNMP to logging. The *Using ping* and *Using traceroute* recipes describe how to use these indispensable networking tools, which are conveniently built into the pfSense web interface. The last several chapters describe the most essential of system services—backup, restore, and update.

Enabling OLSR

OLSR is an implementation of the **Optimized Link State Routing Protocol**, an IP routing protocol optimizing wireless mesh networks. A **mesh network** is a network consisting of two or more nodes, but what makes it unique is the way in which the nodes communicate with each other. The nodes have multiple routes across the network, improving reliability in the face of individual node failures.

This recipe describes how to enable **OLSR (Optimized Link State Routing)** in pfSense.

How to do it...

1. Browse to **Services | OLSR**.
2. Check **Enable OLSR**.
3. Choose an interface (*Ctrl* + click to select multiple interfaces).
4. **Save** the changes.

OLSRD ⓘ

OLSRD Settings

Enable OLSR ☒ Enables the dynamic mesh linking daemon

Link Quality Level 2 ▾

Interfaces WAN LAN DMZ
Select the interfaces that OLSR will bind to. You can use the CTRL or COMMAND key to select multiple interfaces.

How it works...

pfSense's built-in support of OLSR allows configuration through the pfSense GUI. OLSR is highly scalable and highly portable, with an emphasis on reliability. OLSR is commonly used for mobile ad-hoc networks.

There's more...

Enabling the HTTPInfo plugin allows us to view and monitor the status of our OLSR mesh network:

1. Browse to **Services | OLSR**.
2. Check **Enable HTTPInfo Plugin**.
3. Specify an **HTTPInfo Port**.
4. Specify **Allowed Host(s)**.
5. Specify a subnet mask for **Allowed Host(s) Subnet**.
6. **Save** the changes.

Enable HTTPInfo Plugin	<input checked="" type="checkbox"/>	Enables the OLSR stats web server
HTTPInfo Port	<input type="text" value="54321"/>	Port that HTTPInfo will listen on
Allowed host(s)	<input type="text" value="192.168.1.1"/>	Hosts that are allowed to access the HTTPInfo web service.
Allowed host(s) subnet	<input type="text" value="255.255.255.0"/>	Enter the subnet mask in form 255.255.255.0

- Browse to the HTTPInfo plugin site:

olsr.org OLSR daemon

Configuration Routes Links/Topology All About

Version: olsr.org - 0.5.6-r7 (built on 2010-11-21 12:18:20 on FreeBSD_8.0_pfSense_2.0-snaps.pfsense.org)
 OS: FreeBSD
 System time: Sat, 29 Apr 2000 08:03:56
 Olsrd uptime: 00 hours 17 minutes 07 seconds
 HTTP stats(ck/dyn/error/illegal): 0/0/0/0
 Click [here](#) to generate a configuration file for this node.

Variables			
Main address: 192.168.1.1	IP version: 4	Debug level: 2	FIB Metrics: flat
Pollrate: 0.05	TC redundancy: 2	MPPR coverage: 3	NAT threshold: 1.000000
Fisheye: Disabled	TOS: 0x0010	RtTable: 0x00fe/254	RtTableDefault: 0x0000/0
LQ extension: Enabled	LQ level: 2	LQ aging: 0.100000	Willingness: 3

Interfaces		
vr0		
IP: 192.168.1.1	MASK: 255.255.255.0	BCAST: 192.168.1.255
MTU: 1472	WLAN: No	STATUS: UP

Olsrd is configured to run even if no interfaces are available

Plugins	
Name	Parameters
/usr/local/lib/olsrd_httpinfo.so.0.1	KEY, VALUE

Announced HNA entries

(C)2005 Andreas Tormesen
<http://www.olsr.org>

Enabling PPPoE

PPPoE stands for **Point-to-Point Protocol over Ethernet**, a network protocol that allows and encapsulates **Point-to-Point Protocol (PPP)** frames inside Ethernet frames. PPPoE allows two remote clients to connect and conveniently pass data between each other.

This recipe describes how to enable PPPoE on pfSense.

How to do it...

- Browse to **Services | PPPoE Server**.
- Click the "plus" button to add a new PPPoE instance.
- Check **Enable PPPoE Server**.
- Choose an **Interface**.
- Choose a **Subnet Mask**.

6. Set **No. PPPoE Users** to the maximum number of clients we wish to allow.
7. Set **Server Address** to an unused IP address that pfSense will use to serve PPPoE clients.
8. Set **Remote Address Range** to the starting unused IP address. The range will run as far as the maximum number of PPPoE clients specified in step 6.
9. Add a **Description**.
10. Set **DNS Servers** to a particular set or leave them blank for defaults.
11. Add **User(s)**. Click the "plus" button to add a new user. Specify **Username**, **Password**, and **IP**.

User (s)	Username	Password	IP
	john DOE	••••••••	192.168.200.1
	janedoe	••••••••	192.168.200.2

12. **Save** the changes.

Services: PPPoE Server: Edit

PPPoE server configuration

☐ Off

☒ Enable PPPoE server

Interface WAN ▾

Subnet netmask 0 ▾
Hint: 24 is 255.255.255.0

No. PPPoE users 10 ▾
Hint: 10 is ten PPPoE clients

Server address 192.168.1.200
Enter the IP address the PPPoE server should use on its side for all clients.

Remote address range 0.0.0.0
Specify the starting address for the client IP address subnet.

Description My PPPoE Server.

DNS servers
If entered they will be given to all PPPoE clients, else LAN DNS and one WAN DNS will go to all clients

13. **Apply** changes, if necessary.

VPN: PPPoE?

Interface	Local ip	Number of users	Description
WAN	192.168.1.200	10	My PPPoE Server.

How it works...

The PPPoE service is generally used to fill the gap between PPP connections (dial-up) and Ethernet connections (broadband). Internet service providers often want to make use of their existing dial-up authentication systems on a broadband service and PPPoE allows them to do just that.

Enabling RIP

RIP stands for **Routing Information Protocol**, a dynamic routing protocol for local and wide area networks.

This recipe describes how to enable RIP in pfSense.

How to do it...

1. Browse to **Services | RIP**.
2. Check **Enable RIP**.
3. Select an interface (*Ctrl* + click to select multiple interfaces).
4. Select a **RIP Version**.
5. Set a **Password** if using RIP version 2.
6. **Save** the changes.

Services: RIP

ROUTED Settings

Enable RIP

☒

Enables the Routing Information Protocol daemon

Interfaces

WAN

LAN

DMZ

Select the interfaces that RIP will bind to. You can use the CTRL or COMMAND key to select multiple interfaces.

RIP Version

RIP Version 2

Select which RIP version the daemon will listen/advertise using.

RIPv2 password

MyRipPassword

Specify a RIPv2 password. This password will be sent in the clear on all RIPv2 responses received and sent.

Save

How it works...

The RIP protocol was the first dynamic routing protocol to be used in networks and was created for the purpose of sharing routing information between Unix hosts. The RIP protocol broadcasts the complete routing table on all active interfaces on a periodic basis (generally 30 seconds) and not surprisingly, more efficient routing protocols were quickly developed. Enabling the RIP service will allow administrators to support legacy hardware that may require it.

Enabling SNMP


SNMP stands for the **Simple Network Management Protocol**, a standard protocol enabling SNMP clients to query status information on machines that support SNMP.

This recipe describes how to enable the SNMP service in pfSense.

How to do it...

1. Browse to **Services | SNMP**.
2. Check **Enable SNMP Daemon**.
3. Leave **Polling Port** set to the default of UDP 161.
4. Specify a **System Location**.
5. Specify a **System Contact**.

- Specify a **Read Community String**. The community string is roughly equivalent to a password and changing its value will ensure only authorized SNMP clients will be able to query the SNMP information from this machine.



Services: SNMP

SNMP Daemon

Enable

Polling Port	<div>161</div> <div>Enter the port to accept polling events on (default 161)</div>
System location	<div>Home Office</div>
System contact	<div>Matt Williamson</div>
Read Community String	<div>MySecretString</div> <div>The community string is like a password, restricting access to querying SNMP to hosts knowing the community string. Use a strong value here to protect from unauthorized information disclosure.</div>

- Select the **SNMP Modules** to be queried.

Modules

SNMP Modules	<div><input checked="" type="checkbox"/> MibII</div> <div><input checked="" type="checkbox"/> Netgraph</div> <div><input checked="" type="checkbox"/> PF</div> <div><input checked="" type="checkbox"/> Host Resources</div>
--------------	--

Save

- Save** the changes.

How it works...

Enabling SNMP on pfSense will allow administrators to query vital system information from the SNMP client of their choice.

There's more...

SNMP traps are sent by SNMP-enabled devices (like pfSense) to specified servers when a significant event occurs. SNMP trap servers then decide how to process and handle the event, such as e-mailing a network administrator. SNMP traps are useful for network administrators who need to receive alerts quickly, rather than waiting for a potentially long polling cycle to detect any issues.

To specify an SNMP trap server in pfSense:

1. Browse to **Services | SNMP**.
2. Check **Enable SNMP Traps**.
3. Specify the **Trap Server Name**.
4. Specify the **Trap Server Port**.
5. Specify the **SNMP Trap String**.

SNMP Traps Enable	
Trap server	<input type="text" value="trapserver1.mydomain.com"/> <small>Enter trap server name</small>
Trap server port	<input type="text" value="162"/> <small>Enter the port to send the traps to (default 162)</small>
Enter the SNMP trap string	<input type="text" value="MyTrapServerString"/> <small>Trap string</small>

6. Save the changes.

See also

- ▶ PfSense SNMP Daemon documentation
http://doc.pfsense.org/index.php/SNMP_Daemon

Enabling UPnP and NAT-PMP

UPnP and NAT-PMP are simply different implementations of the same concept, automated NAT port mapping. These protocols are designed to allow clients to automatically configure the port-forwarding rules of a router/firewall. A common example is to enable UPnP so that an Xbox 360 can successfully connect to Xbox Live.

Generally, the UPnP protocol is used by Microsoft systems while the NAT-PMP is used by Apple systems.

This recipe describes how to enable UPnP and NAT-PMP in pfSense.

How to do it...

1. Browse to **Services | UPnP & NAT-PMP**.
2. Check **Enable UPnP & NAT-PMP**.
3. Check **Allow UPnP Port Mapping**, **Allow NAT-PMP Port Mapping**, or both.
4. Select the **Interface(s)** which will be applied (*Ctrl* + click to select multiple interfaces).

Services: UPnP & NAT-PMP

UPnP & NAT-PMP Settings

Enable UPnP & NAT-PMP ☒

Allow UPnP Port Mapping ☒ This protocol is often used by Microsoft-compatible systems.

Allow NAT-PMP Port Mapping ☐ This protocol is often used by Apple-compatible systems.

Interfaces (generally LAN)

WAN
LAN
PUB

You can use the CTRL or COMMAND key to select multiple interfaces.

5. **Save** the changes.





How it works...

Enabling UPnP and NAT-PMP allows compatible devices to function properly on a given network without needing to define particular port-forwarding rules.

There's more...

The following optional features are available for the UPnP & NAT-PMP services in pfSense:





- ▶ Specify a **Maximum Download Speed** for UPnP and NAT-PMP devices
- ▶ Specify a **Maximum Upload Speed** for UPnP and NAT-PMP devices
- ▶ Specify to **Override the WAN Address** for UPnP and NAT-PMP devices
- ▶ Specify a particular **Traffic Shaping Queue** for UPnP and NAT-PMP clients

Maximum Download Speed (Kbits/second)	 1500
Maximum Upload Speed (Kbits/second)	 500
Override WAN address	
Traffic Shaping Queue	

- ▶ **Enable Log Packets** handled by UPnP and NAT-PMP clients
- ▶ Use **System Uptime** instead of UPnP and NAT-PMP service uptime
- ▶ By **Default Deny Access** to UPnP and NAT-PMP

Log packets handled by UPnP & NAT-PMP rules?	<input checked="" type="checkbox"/>
Use system uptime instead of UPnP & NAT-PMP service uptime?	<input type="checkbox"/>
By default deny access to UPnP & NAT-PMP?	<input type="checkbox"/>

- ▶ Define up to four **User specified permissions**

User specified permissions 1	 Format: [allow or deny] [ext port or range] [int ipaddr or ipaddr/cdir] [int port or range] Example: allow 1024-65535 192.168.0.0/24 1024-65535
User specified permissions 2	 Format: [allow or deny] [ext port or range] [int ipaddr or ipaddr/cdir] [int port or range]
User specified permissions 3	 Format: [allow or deny] [ext port or range] [int ipaddr or ipaddr/cdir] [int port or range]
User specified permissions 4	 Format: [allow or deny] [ext port or range] [int ipaddr or ipaddr/cdir] [int port or range]

Security warning

Allowing devices to make/modify their own firewall rules has some serious security implications. Microsoft's flagship firewall system ISA (and the newer TMG) refuses to even support these protocols. If you need to enable these services, please be aware of the risk. I would dedicate a separate interface for these services (and other risky traffic). You can see in the screenshots that I've only enabled UPnP for my PUB interface. This is an interface that I treat as very insecure, but it's useful for playing video games or allowing guests to surf the web freely.

See also


- ▶ PfSense UPnP Documentation
http://doc.pfsense.org/index.php/What_is_UPNP%3F
- ▶ Wikipedia UPnP Article
http://en.wikipedia.org/wiki/Universal_Plug_and_Play
- ▶ Wikipedia NAT-PMP Article
http://en.wikipedia.org/wiki/NAT_Port_Mapping_Protocol

Enabling OpenNTPD

The OpenNTPD service will serve date and time requests to clients that request them. This recipe describes how to enable the OpenNTPD service in pfSense.

How to do it...

1. Browse to **Services** | **OpenNTPD**.
2. Check **Enable** to enable the NTP daemon service.
3. Select the interface(s) the NTP daemon service will listen on.



NTP server ?

Enable ☒ Check this to enable the NTP server.

Interface WAN
LAN
PUB
DMZ Select the interface(s) the NTP server will listen on.

Save

4. **Save** the changes.

How it works...

OpenNTPD is an open-source implementation of the Network Time Protocol service. Devices within your network can now query the pfSense firewall with NTP and receive accurate time data from it.



Client machines can take a few hours to become fully synchronized with the OpenNTPD service. Be patient.

See also

- ▶ PfSense NTPD Documentation
http://doc.pfsense.org/index.php/NTP_Server_%28OpenNTPD%29
- ▶ OpenNTPD.org
<http://www.openntpd.org/>
- ▶ Wikipedia OpenNTPD Article
<http://en.wikipedia.org/wiki/OpenNTPD>

Enabling Wake On LAN (WOL)

pfSense can send a **Wake-on-LAN** packet (also known as a **magic packet**) to a compatible device to "wake it up" out of suspended/sleep mode. This recipe describes how to use the Wake-on-LAN facility in pfSense.


How to do it...

1. Browse to **Services | Wake on LAN**.
2. Select the **Interface** which contains the device we'd like to wake up.
3. Enter the device's **MAC address**.


Services: Wake on LAN	
Wake on LAN	
Interface	<div>LAN ▼</div> <p>Choose which interface the host to be woken up is connected to.</p>
MAC address	<div> 90:84:0d:9d:fc:57 </div> <p>Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx</p>
<div>Send</div>	

4. Click **Send**.

Services: Wake on LAN

 Sent magic packet to 90:84:0d:9d:fc:57.
 Close

Wake on LAN

Interface	<div>LAN</div> <div>Choose which interface the host to be woken up is connected to.</div>
MAC address	<div>  90:84:0d:9d:fc:57 </div> <div>Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx</div>

Send

How it works...

The Wake-on-LAN service can send "magic packets" to any network devices that support and are properly configured for Wake on LAN. When a properly configured device receives a magic packet, it will "wake the machine up" out of sleep or standby mode.



Note that on older hardware, properly configuring an NIC can involve attaching a special WOL cable to the motherboard and then enabling WOL in that machine's BIOS.

There's more...

You can store the MAC addresses of any machines that support Wake on LAN:

1. Browse to **Services | Wake on LAN**.
2. Click the "plus" button to add a WOL Mac Address entry.
3. Select the **Interface** that contains the device.
4. Specify the device's **MAC address**.
5. Add a **Description**.

Services: Wake on LAN: Edit

Edit WOL entry


Interface	<div>LAN ▼</div> Choose which interface this host is connected to.
MAC address	<div>90:84:0d:9d:fc:57</div> Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx
Description	<div>Matt's Desktop</div> You may enter a description here for your reference (not parsed).

6. **Save** the changes.


Interface	MAC address	Description	
LAN	90:84:0d:9d:fc:57	Matt's Desktop	 
LAN	00:26:08:ae:b3:3a	Matt's Laptop	 


7. Click the **MAC address** of any of the stored clients to send a magic packet.

Services: Wake on LAN





 Sent magic packet to 00:26:08:ae:b3:3a.

Wake on LAN

Interface	<div>WAN ▼</div> Choose which interface the host to be woken up is connected to.
MAC address	<div></div> Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx

Wake all clients at once: 

Or Click the MAC address to wake up an individual device:

Interface	MAC address	Description	
LAN	90:84:0d:9d:fc:57	Matt's Desktop	 
LAN	00:26:08:ae:b3:3a	Matt's Laptop	 

Note:
This service can be used to wake up (power on) computers by sending special "Magic Packets". The NIC in the computer that is to be woken up must support Wake on LAN and has to be configured properly (WOL cable, BIOS settings).

Wake All

Instead of waking clients individually, there may be times when we want to wake them all up at once—simply click the **Wake All** button.

Services: Wake on LAN

Sent magic packet to 90:84:0d:9d:fc:57 (Matt's Desktop).
Sent magic packet to 00:26:08:ae:b3:3a (Matt's Laptop).

Wake on LAN

Interface

WAN

Choose which interface the host to be woken up is connected to.

MAC address

Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx

Send

Wake all clients at once:

Or Click the MAC address to wake up an individual device:

Interface	MAC address	Description
LAN	90:84:0d:9d:fc:57	Matt's Desktop
LAN	00:26:08:ae:b3:3a	Matt's Laptop

Note:
This service can be used to wake up (power on) computers by sending special "Magic Packets". The NIC in the computer that is to be woken up must support Wake on LAN and has to be configured properly (WOL cable, BIOS settings).

See also

- ▶ PfSense Wake-on-LAN Documentation
http://doc.pfsense.org/index.php/Wake_on_LAN
- ▶ Wikipedia Wake-on-LAN Article
<http://en.wikipedia.org/wiki/Wake-on-LAN>

Enabling external logging (syslog server)

Syslog is a standardized system for logging all types of information. Syslog client and server implementations exist for all major operating systems.

Most Linux distributions are already running the syslog service, so setting up a centralized server is only a matter of deciding which machine to use, configuring that machine to listen for syslog data on the network, and then configuring all other machines to direct syslog messages to that server.

This recipe describes how to configure pfSense to write logs to an external syslog server.

Getting ready

To turn a Windows machine into a centralized syslog server, take a look at the Kiwi Syslog Server and Log Viewer.

How to do it...

1. Browse to **Status | System Logs**.
2. Click the **Settings** tab.
3. Check **Enable syslog'ing to remote syslog server**.
4. Specify the IP addresses of up to three remote syslog servers.
5. Check **Everything** to record all messages or select specific events.

The screenshot shows the 'Enable syslog'ing to remote syslog server' settings page in pfSense. At the top, there is a checkbox labeled 'Enable syslog'ing to remote syslog server' which is checked. Below this, there is a section titled 'Remote syslog servers' with three input fields for 'Server 1', 'Server 2', and 'Server 3'. The 'Server 1' field contains the IP address '192.168.1.231'. Below these fields is a label 'IP addresses of remote syslog servers'. Underneath, there is a list of event types with checkboxes: 'system events', 'firewall events', 'DHCP service events', 'Portal Auth', 'PPTP VPN events', and 'Everything'. The 'Everything' checkbox is checked. At the bottom of the form is a 'Save' button. Below the 'Save' button is a 'Note' section with the text: 'syslog sends UDP datagrams to port 514 on the specified remote syslog server. Be sure to set syslogd on the remote server to accept syslog messages from pfSense.'

6. **Save** the changes.

How it works...

By writing logs to an external syslog server, we have taken significant weight off the resources of our pfSense machine. This can have a very positive effect on many pfSense boxes that are light on memory and hard drive space, and is especially useful for machines using limited-lifetime disks such as CompactFlash drives.

There's more...

If you are *not* configuring an external syslog server, the following internal logging options are available in pfSense:

- ▶ Show log entries in reverse order (newest entries on top)
- ▶ Number of log entries to show
- ▶ Log packets blocked by the default rule
- ▶ Show raw filter logs
- ▶ Disable writing log files to the local RAM disk

See also

- ▶ PfSense Log Settings Documentation
http://doc.pfsense.org/index.php/Log_Settings
- ▶ Wikipedia Syslog Article
<http://en.wikipedia.org/wiki/Syslog>
- ▶ Kiwi Syslog Server and Log Viewer
<http://www.kiwisyslog.com/>

Using ping

pfSense exposes the ping service that's included on almost all operating systems. This can be handy for administrators since pfSense can ping on any machine from any specified interface. This recipe describes how to use the ping service in pfSense.

How to do it...

1. Browse to **Diagnostics | Ping**.
2. Set **Host** to the IP Address or hostname of the machine we're trying to ping.
3. Choose the **Interface** to initiate the ping from.
4. Select a **Count**, the default of 3 is generally adequate.

Diagnostics: Ping

Ping

Host	<input type="text" value="192.168.1.101"/>
Interface	LAN ▼
Count	3 ▼

Ping

5. Press the **Ping** button.

Diagnostics: Ping

Ping

Host	<input type="text" value="192.168.1.101"/>
Interface	LAN ▼
Count	3 ▼

Ping

Ping output:

```

PING 192.168.1.101 (192.168.1.101) from 192.168.1.1: 56 data bytes
64 bytes from 192.168.1.101: icmp_seq=0 ttl=64 time=0.433 ms
64 bytes from 192.168.1.101: icmp_seq=1 ttl=64 time=0.441 ms
64 bytes from 192.168.1.101: icmp_seq=2 ttl=64 time=0.405 ms

-- 192.168.1.101 ping statistics --
3 packets transmitted, 3 packets received, 0.0% packet loss
round-trip min/avg/max/stddev = 0.405/0.426/0.441/0.015 ms
  
```

How it works...

The ping utility allows administrators to ping any machine on any interface, *from* any interface. Ping is an indispensable tool and having it built into the firewall's web interface is a great tool for administrators.

See also

- ▶ PfSense Ping Host Documentation
http://doc.pfsense.org/index.php/Ping_Host
- ▶ Wikipedia Ping Article
<http://en.wikipedia.org/wiki/Ping>

Using traceroute

.pfSense exposes the traceroute service that's included on almost all operating systems. This can be handy for administrators who need to perform an ad-hoc traceroute.

This recipe describes how to use the traceroute utility in pfSense.

How to do it...

1. Browse to **Diagnostics | Traceroute**.
2. Set **Host** to the IP Address or hostname of the machine we're trying to trace.
3. Choose the **Maximum number of hops** for the trace to jump.
4. Optionally check **Use ICMP**.



Traceroute	
Host	<input type="text" value="google.com"/>
Maximum number of hops	<input type="text" value="18"/>
Use ICMP	<input type="checkbox"/>

Traceroute

Note: Traceroute may take a while to complete. You may hit the Stop button on your browser at any time to see the progress of failed traceroutes.

5. Click the **Traceroute** button.

Diagnostics: Traceroute

Traceroute

Host	<input type="text" value="google.com"/>
Maximum number of hops	<input type="text" value="18"/> ▼
Use ICMP	<input type="checkbox"/>

Traceroute

Note: Traceroute may take a while to complete. You may hit the Stop button on your browser at any time to see the progress of failed traceroutes.

Traceroute output:

```

1 10.240.176.13 (10.240.176.13) 9.819 ms 6.781 ms 5.817 ms
2 dstswr2-vlan2.rh.nbrgnj.cv.net (67.83.246.162) 7.783 ms 8.320 ms 6.748 ms
3 rtr2-ge1-14.mhe.prnynj.cv.net (67.83.246.133) 9.923 ms 9.245 ms 9.716 ms
4 64.15.2.81 (64.15.2.81) 12.427 ms 11.448 ms 10.172 ms
5 64.15.0.249 (64.15.0.249) 12.698 ms
  64.15.0.145 (64.15.0.145) 11.861 ms 11.655 ms
6 * * *
7 72.14.238.232 (72.14.238.232) 12.564 ms 11.508 ms 14.527 ms
8 216.239.48.92 (216.239.48.92) 13.084 ms 11.738 ms 9.703 ms
9 lga15s16-in-f104.1e100.net (173.194.35.104) 10.809 ms 13.138 ms 11.576 ms

```

Note: Multi-wan is not supported from this utility currently.

How it works...

The traceroute utility allows administrators to perform an ad-hoc trace directly from the pfSense web interface.



Traceroute can sometimes take a long time to complete. Click the browser's stop button at any time to cancel the traceroute and display the results.

See also

- ▶ pfSense Traceroute Documentation
<http://doc.pfsense.org/index.php/Traceroute>
- ▶ Wikipedia Traceroute Article
<http://en.wikipedia.org/wiki/Traceroute>

Backing up the configuration file


Backing up configuration files is an essential part of any administrator's position. This recipe describes how to back up the pfSense configuration file.

Getting ready...

pfSense configuration files are stored in a plain-text XML format by default, but it also gives you an option to encrypt them.

How to do it...

1. Browse to **Diagnostics | Backup/restore**.
2. Select the **Backup/Restore** tab.
3. Set the **Backup area** to **ALL**. For a list of all available areas, see the following *Backup areas* section.
4. Leave **Do not backup package information** unchecked.
5. Leave **Do not backup RRD data** checked.



Diagnostics: Backup/restore

Config History **Backup/Restore**

Backup configuration

Click this button to download the system configuration in XML format.

Backup area: **ALL**


☐ Do not backup package information.

☐ Encrypt this configuration file.

☒ Do not backup RRD data (NOTE: RRD Data can consume 4+ megabytes of config.xml space!)

Download configuration

6. Click **Download configuration**.
7. **Save** the file to a secure location.



How it works...

pfSense allows an administrator to download the entire pfSense configuration in a single XML file to any local or networked drive.

There's more...

Some passwords will be stored in plain text! If this is a concern, be sure to check the **Encrypt this configuration file** option and specify a password.



Backup areas

Currently in pfSense 2.0, the following backup areas are available:

- ▶ ALL
- ▶ Aliases
- ▶ DNS Forwarder
- ▶ DHCP Server
- ▶ Firewall Rules
- ▶ Interface
- ▶ IPSec
- ▶ NAT
- ▶ Package Manager
- ▶ PPTP Server
- ▶ Scheduled Tasks
- ▶ Syslog
- ▶ System
- ▶ System Tunables
- ▶ SNMP Server

See also

- ▶ PfSense Configuration Backup/Restore Documentation
http://doc.pfsense.org/index.php/Configuration_Backup_and_Restore

Restoring the configuration file


This recipe describes how to restore the pfSense configuration file.

Getting ready...

Restoring configuration files is an essential part of any administrator's position. pfSense configuration files are stored in a plain-text XML format by default, but an encryption option is available.

How to do it...

1. Browse to **Diagnostics | Backup/restore**.
2. Select the **Backup/Restore** tab.
3. Set the **Restore area** to **ALL**. For a list of all available areas, see the following *Restore areas* section:



The screenshot shows the 'Restore configuration' page. At the top, it says 'Open a configuration XML file and click the button below to restore the configuration.' Below this is a 'Restore area:' dropdown menu set to 'ALL'. There is a text input field containing the path '/home/matt/Desktop/config-pfsense.bunkerhollow.c' and a 'Browse...' button. A checkbox labeled 'Configuration file is encrypted.' is unchecked. A 'Restore configuration' button is at the bottom. A red 'Note:' box at the bottom states 'The firewall will reboot after restoring the configuration.'

4. Click **Restore configuration** and pfSense will reboot.



The screenshot shows the 'Diagnostics: Backup/restore' page. A red message box at the top says 'The firewall configuration has been changed. The firewall is now rebooting.' with a 'Close' button. A help icon (?) is in the top right corner.

How it works...

pfSense allows an administrator to restore the entire pfSense configuration from a single XML file.

There's more...

If the configuration file was encrypted, be sure to check the **Configuration file is encrypted** option and specify the correct password:

Restore areas

Currently in pfSense 2.0 the following back up areas are available:

- ▶ ALL
- ▶ Aliases
- ▶ Captive Portal
- ▶ Captive Portal Vouchers
- ▶ DNS Forwarder
- ▶ DHCP Server
- ▶ Firewall Rules
- ▶ Interface
- ▶ IPSec
- ▶ NAT
- ▶ OpenVPN
- ▶ Package Manager
- ▶ PPTP Server
- ▶ Scheduled Tasks
- ▶ Static Routes
- ▶ Syslog
- ▶ System

- ▶ System Tunables
- ▶ SNMP Server
- ▶ Traffic Shaper
- ▶ VLANs
- ▶ Wake on LAN

See also

- ▶ PfSense Configuration Backup/Restore Documentation
http://doc.pfsense.org/index.php/Configuration_Backup_and_Restore

Configuring automatic configuration file backup

This recipe describes how to configure pfSense to automatically back up its configuration file.

Getting ready

Users with a pfSense support subscription can configure automated backup to external pfSense servers using their `portal.pfsense.org` login credentials. Currently, only paid support subscribers have access to this feature.

How to do it...

1. Browse to **Diagnostics | AutoConfigBackup**.
2. Click the **Settings** tab.
3. Enter our **Subscription Username**.
4. Enter our **Subscription Password**.
5. Confirm **Subscription Password**.
6. Enter our **Encryption Password**.

7. Confirm **Encryption Password**.

Diagnostics: Auto Configuration Backup

Settings Restore Backup now Stats

Subscription Username
Enter the subscription username for portal.pfsense.org

Subscription Password
Enter the password for portal.pfsense.org

Enter Password again

Encryption Password
This password will be used to encrypt config.xml before sending to portal.pfsense.org. Do not share the password and keep it safe!

Encryption Password again
Enter the encryption password again.

Test connection ☐
Check this box to test the connection to portal.pfsense.org.

Change

8. **Save** the changes.

How it works...

Automated backups can now be securely stored on a set of external pfSense servers. This is convenient for users to have a safe external backup location, as well as for support staff, which will be able to track configuration changes while troubleshooting issues.

There's more...

A pfSense support subscription makes automated backup available. Also, restores can be done directly from the pfSense servers and backup/restore statistics are available directly from the **Stats** tab.

See also

- ▶ pfSense Automated Configuration Backup Documentation
<http://doc.pfsense.org/index.php/AutoConfigBackup>
- ▶ pfSense Premium Portal
<https://portal.pfsense.org/>

Updating pfSense firmware


This recipe describes how to update the pfSense firmware.

Getting ready


Let's be sure to make a backup of our current configuration file before we proceed with a complete system upgrade.

How to do it...

1. Browse to **System | Firmware**.
2. Click the **Auto Update** tab.
3. Click **Invoke Auto Upgrade**.




4. Observe the download status.



- Once the download is complete, pfSense will upgrade itself and reboot.



- On the first login after the system has rebooted, we'll be redirected to **Package Manager** status page.




How it works...

pfSense will contact a web service at `http://pfsense.org/` to determine the latest firmware version, and to download that firmware if needed.


There's more...

pfSense also allows for a manual firmware upgrade, outlined in the steps below:

1. Download the appropriate version from `http://pfsense.org/` and save it locally.



2. Browse to **System | Firmware**.
3. Click the **Manual Update** tab.



4. Click the **Enable firmware upload** button.

- Click **Browse** to locate the firmware file we've downloaded.

System: Firmware

Manual Update
Auto Update
Updater Settings

Invoke pfSense Manual Upgrade

Click "Enable firmware upload" below, then choose the image file (pfSense-*.img.gz) to be uploaded. Click "Upgrade firmware" to start the upgrade process.

Disable firmware upload

Firmware image file: 44-nanobsd-upgrade.img.gz Browse...

NOTE: You must upload a .img.gz image, not an uncompressed image!

Upgrade firmware

Warning:
DO NOT abort the firmware upgrade once it has started. The firewall will reboot automatically after storing the new firmware. The configuration will be maintained.

- Click **Upgrade firmware**.

System: Firmware


The firmware is now being updated. The firewall will reboot automatically.
Close

Upgrade in progress

Any attempt to access the pfSense web interface while an upgrade is in progress will redirect us to the following page and animation. Once the upgrade is complete, the machine will reboot.

System: Firmware: Manual Update

An upgrade is currently in progress.

The firewall will reboot when the operation is complete.


Close

System Dashboard shortcut

If a new version of pfSense is available, an **Update available** notification will be displayed on the **Status Dashboard** homepage in the **Version** section of **System Information**.



See also

- ▶ The *Backing up the configuration file* recipe
- ▶ pfSense Firmware Update Documentation
http://doc.pfsense.org/index.php/Firmware_Updates

A

Monitoring and Logging

In this chapter, we will cover:

- ▶ Customizing the Status Dashboard
- ▶ Monitoring current traffic
- ▶ Configuring SMTP e-mail notifications
- ▶ Viewing system logs
- ▶ Configuring an external syslog server
- ▶ Viewing RRD graphs
- ▶ Viewing DHCP leases
- ▶ Monitoring the packet filter with pfInfo
- ▶ Monitoring traffic with pfTop
- ▶ Monitoring system activity

Introduction


Once pfSense is up and running, it's important to understand how to properly monitor the system. Learning to use the status monitor and logging tools built into pfSense will make an administrator's life all the much easier. The following recipes describe how to monitor and log the majority of features available within pfSense.

Customizing the Status Dashboard


This recipe describes how to personally configure the **Status Dashboard**.

How to do it...

1. Browse to **Status | Dashboard**.
2. Click the "plus" button to add a widget:



3. Click the wrench button to configure settings for a particular widget.



- Click the "minimize" button to collapse a widget, or the "close" button to remove one from the screen.
- Drag and drop widgets by their title to change their position on the screen.

Status: Dashboard

Save Settings

System Information

Services Status

Service	Description	Status
dnsmasq	DNS Forwarder	Running
ntpd	NTP clock sync	Running
dhcpcd	DHCP Service	Running
miniupnpd	UPnP Service	Running

Interfaces

Interface	IP Address	Speed
WAN (DHCP)		100baseTX <full-duplex>
LAN	172.22.22.1	1000baseT <full-duplex>
PUB	172.22.23.1	1000baseT <full-duplex>

Traffic Graphs

Refresh Interval: 10 Seconds
 Note: changing this setting will increase CPU utilization
 Save Settings

Current WAN Traffic

In 526 Kbps
 Out 487 Kbps

1/9/2011 14:42:10
 Switch to bytes/s
 Autoscale (yep)
 Graph shows last 1200 seconds

Current LAN Traffic

Current PUB Traffic

- Save the settings.
- Apply changes, if necessary.

How it works...

The **Status Dashboard** is among the many new features added to pfSense 2.0. By customizing the dashboard to display the information you are interested in, administration becomes much easier. If properly configured, the dashboard may be the only page an administrator may need to visit to accomplish many common tasks.

There's more...


Many of the widgets available on the dashboard also have a corresponding status item that can be found in the **Status** drop-down menu.

Monitoring current traffic

This recipe describes how to monitor current incoming and outgoing traffic in pfSense.

How to do it...

1. Browse to **Status | Traffic Graph**.
2. Select an **Interface** to monitor.



How it works...

The traffic graph shows real-time information of all traffic flowing to and from a particular interface. The table to the right will show the traffic information for the top few devices on the network.



Your browser must support SVG graphics, as Firefox does. If your browser doesn't support SVG graphics, install the Adobe SVG Viewer.

See also

- ▶ pfSense Traffic Graph Documentation
http://doc.pfsense.org/index.php/Traffic_Graph
- ▶ Adobe SVG Viewer
<http://www.adobe.com/svg/viewer/install/>

Configuring SMTP e-mail notifications

This recipe describes how to configure SMTP settings to send notification e-mails.

Getting ready

Sending e-mails from pfSense requires access to an SMTP server

How to do it...

1. Browse to **System | Advanced**.
2. Click the **Notifications** tab.
3. Enter the **IP Address of the E-Mail server**.
4. Enter the **SMTP Port of the E-Mail server**.
5. Enter the **From e-Mail address**.
6. Enter the **Notification E-Mail address**.
7. Enter the **Notification E-Mail auth username**.
8. Enter the **Notification E-Mail auth password**.

SMTP E-Mail	
IP Address of E-Mail server	<input type="text" value="smtp.mydomain.com"/> <small>This is the IP address of the SMTP E-Mail server that will be used to send notifications to.</small>
SMTP Port of E-Mail server	<input type="text" value="25"/> <small>This is the port of the SMTP E-Mail server, typically 25 or 587 (submission).</small>
From e-mail address	<input type="text" value="johndoe@mydomain.com"/> <small>This is the e-mail address that will appear in the from field.</small>
Notification E-Mail address	<input type="text" value="me@mydomain.com"/> <small>Enter the e-mail address that you would like email notifications sent to.</small>
Notification E-Mail auth username (optional)	<input type="text" value="johndoe"/> <small>Enter the e-mail address username for SMTP authentication.</small>
Notification E-Mail auth password	<input type="password" value="....."/> <small>Enter the e-mail address password for SMTP authentication.</small>
<input type="button" value="Save"/>	

9. **Save** the changes.
10. **Apply** changes, if necessary.

How it works...

pfSense will send an e-mail notification using the information supplied to notify administrators of significant system events.

There's more...

Once our settings are saved, a test e-mail will be sent automatically. If you do not receive the test e-mail, check the system logs for more information. Browse to the **Status | System Logs | System** tab and look for any e-mail-related log entries:



The screenshot shows the pfSense web interface. At the top, the breadcrumb is "Status: System logs: System". Below this is a tabbed interface with tabs for "System", "Firewall", "DHCP", "Portal Auth", "IPsec", "PPP", "VPN", "Load Balancer", "OpenVPN", "OpenNTPD", and "Settings". The "System" tab is selected. Below the tabs is a section titled "Last 50 system log entries" with a red header. It contains a table of log entries:

Time	Message
Jan 9 15:47:36	php: /system_advanced_notifications.php: Could not send the message to me@mydomain.com -- Error: could not connect to the host "smtp.mydomain.com": ??
Jan 9 15:46:36	check_reload_status: syncing firewall
Jan 9 15:14:40	check_reload_status: syncing firewall
Jan 9 15:13:35	sshlockout[47037]: sshlockout/webConfigurator v3.0 starting up

Viewing system logs

This recipe describes how to view the pfSense system logs.

How to do it...

1. Browse to **Status | System logs**.
2. Click the **Settings** tab.
3. Check **Show log entries in reverse order (newest entries on top)**.
4. **Save** the changes.
5. Click the **DHCP** tab (for example) to view the most recent DHCP events:

Status: System logs: DHCP ?	
System	Firewall
DHCP	Portal Auth
IPsec	PPP
VPN	Load Balancer
OpenVPN	OpenNTPD
Settings	
Last 50 DHCP service log entries	
Jan 9 16:53:44	dhcpd: DHCPACK on 172.22.23.192 to 00:26:08:ae:b3:3a (Alexs-iPhone) via em2
Jan 9 16:53:44	dhcpd: DHCPREQUEST for 172.22.23.192 from 00:26:08:ae:b3:3a (Alexs-iPhone) via em2
Jan 9 16:53:43	dhcpd: DHCPACK on 172.22.23.197 to 90:84:0d:9d:fc:57 (Matts-iPhone) via em2
Jan 9 16:53:43	dhcpd: DHCPREQUEST for 172.22.23.197 from 90:84:0d:9d:fc:57 (Matts-iPhone) via em2
Jan 9 16:49:24	dhcpd: DHCPACK on 172.22.22.206 to 00:1b:a9:26:b8:90 via em3
Jan 9 16:49:24	dhcpd: DHCPREQUEST for 172.22.22.206 from 00:1b:a9:26:b8:90 via em3

How it works...

pfSense records significant events and logs them internally. The **System logs** menu item allows us to view the logs to help troubleshoot a variety of administrative issues.

The following sections describe how configure the alternate log views provided for firewall events.

There's more...

Logging information is gathered and displayed for the following services:

- ▶ System
- ▶ Firewall
- ▶ DHCP
- ▶ Portal Auth
- ▶ IPsec
- ▶ PPP
- ▶ VPN
- ▶ Load Balancer
- ▶ OpenVPN
- ▶ OpenNTPD



If logging on to an external syslog server, there won't be any data on these pages.

Firewall log: Normal View

The following is a screenshot of the normal firewall log view:

Status: System logs: Firewall

System

Firewall

DHCP

Portal Auth

IPsec

PPP

VPN

Load Balancer

OpenVPN

OpenNTPD

Settings

Normal View | Dynamic View | Summary View

Last 50 firewall log entries. Max(50)

Act	Time	If	Source	Destination	Proto
	Jan 9 16:57:51	WAN	69.178.94.80:26040	:51413	UDP
	Jan 9 16:57:50	WAN	74.41.254.202:49736	:47241	TCP:S
	Jan 9 16:57:50	WAN	80.183.1.94:17215	:3929	TCP:RA
	Jan 9 16:57:50	WAN	91.144.113.245:50793	:51413	UDP
	Jan 9 16:57:50	WAN	92.255.251.75:54356	:52472	UDP
	Jan 9 16:57:48	WAN	69.178.94.80:26040	:51413	UDP

Firewall log: Dynamic View

The following is a screenshot of the dynamic firewall log view:

Diagnostics: System logs: Firewall

System

Firewall

DHCP

Portal Auth

IPsec

PPP

VPN

Load Balancer

OpenVPN

OpenNTPD

Settings

Normal View

Dynamic View


Summary View

Last 50 records; Pause: ☐

Act	Time	If	Source	Destination	Proto
	Jan 9 17:02:49	WAN	68.80.155.72:28286	:51413	UDP
	Jan 9 17:02:49	WAN	78.30.158.253:12608	:51413	UDP
	Jan 9 17:02:49	WAN	217.16.128.36:44043	:20942	UDP
	Jan 9 17:02:48	WAN	10.240.176.13:67	55:68	UDP
	Jan 9 17:02:48	WAN	178.37.102.45:4758	:51413	UDP

Firewall log: Summary View

The following is a screenshot of the summary firewall log view:



See also

- [The Configuring an external syslog server recipe](#)

Configuring an external syslog server

This recipe describes how to configure pfSense to use an external logging server.

Getting ready

To configure pfSense to use a separate server for logging, we obviously need a separate logging server to accomplish this. The following sections describe how to create a syslog server on each of the major operating systems.

How to do it...

1. Browse to **Status | System Logs**.
2. Click the **Settings** tab.
3. Check **Enable syslog'ing to remote syslog server**.
4. Enter the IP address(es) of our external syslog servers.
5. Check the types of events to be logged.

The screenshot shows the 'Enable syslog'ing to remote syslog server' configuration page in pfSense. At the top, there is a checkbox labeled 'Enable syslog'ing to remote syslog server' which is checked. Below this, there is a section titled 'Remote syslog servers' with three input fields for 'Server 1', 'Server 2', and 'Server 3'. The first field contains the IP address '192.168.1.151'. Below these fields is a label 'IP addresses of remote syslog servers'. Underneath, there is a list of event types with checkboxes: 'system events', 'firewall events', 'DHCP service events', 'Portal Auth', 'PPTP VPN events', and 'Everything'. The 'Everything' checkbox is checked. At the bottom of the form is a 'Save' button. Below the button, there is a red 'Note' that reads: 'syslog sends UDP datagrams to port 514 on the specified remote syslog server. Be sure to set syslogd on the remote server to accept syslog messages from pfSense.'

6. **Save** the changes.
7. **Apply** changes, if necessary.

How it works...

Once configured, pfSense will send event logs to an external server instead of logging them locally. This is a great way to free up resources on a pfSense machine and to save larger and more detailed logs to a machine with much more disk space.

Running a syslog service in Linux/Mac OS

Almost all Linux and Mac OS distributions already include the **syslogd** service. Visit the following page for more information: <http://linux.die.net/man/8/syslogd>.

Running a syslog service in Windows

Download and install the Kiwi Syslog Server for Windows from <http://www.kiwisyslog.com>.

See also


- ▶ The *Viewing system logs* recipe
- ▶ Linux syslogd documentation
<http://linux.die.net/man/8/syslogd>
- ▶ Kiwi Syslog Server
<http://www.kiwisyslog.com>

Viewing RRD graphs

This recipe describes how to view RRD graphs from within pfSense.

How to do it...

1. Browse to **Status | RRD Graphs**.
2. Choose the **System** tab.
3. Select the **Graphs**, **Style**, and **Period** of the data we'd like displayed.



How it works...


pfSense records system data and uses the open-source RRD toolset to present that data graphically. Analyzing system data with the RRD graphs is a great way to monitor and troubleshoot all sorts of administrative issues.

pfSense can analyze and display the following information in RRD graph format.

System

The **System** tab gathers and displays hardware load information.


- ▶ Throughput
- ▶ States
- ▶ Process
- ▶ Memory
- ▶ All



Traffic

The **Traffic** tab gathers and displays network throughput information for each of the systems interfaces.


- ▶ Outbound
- ▶ WAN
- ▶ LAN
- ▶ Optional Interface(s)
- ▶ OpenVPN
- ▶ IPsec
- ▶ All



Packets

The **Packets** tab gathers and displays packet throughput information for each of the systems interfaces.


- ▶ Outbound
- ▶ WAN
- ▶ LAN
- ▶ Optional Interface(s)
- ▶ OpenVPN
- ▶ IPSec
- ▶ All



Quality

The **Quality** tab gathers and displays packet loss information for each of the systems interfaces.


- ▶ Outbound
- ▶ WAN
- ▶ Gateway(s)
- ▶ All



VPN


The **VPN** tab gathers and display VPN throughput information (if applicable).

- ▶ OpenVPN
- ▶ IPSec
- ▶ PPTP
- ▶ All



Custom

Choose any previous graph and specify starting and ending timestamps.



See also

- RRDTool

<http://www.mrtg.org/rrdtool/>

Viewing DHCP leases

This recipe describes how to view DHCP leases served by pfSense.


How to do it...
















1. Browse to **Status | DHCP leases**:

Status: DHCP leases 

IP address	MAC address	Hostname	Start	End	Online	Lease Type	
172.22.23.197	90:84:0d:9d:fc:57	Matts-iPhone	2011/01/09 20:56:00	2011/01/10 20:56:00	online	active	 
172.22.23.199	00:1d:e0:a7:8e:c5	Thinkpad	2011/01/09 20:35:54	2011/01/09 22:35:54	offline	active	  
172.22.23.192	00:26:08:ae:b3:3a	Alexs-iPhone	2011/01/09 20:24:25	2011/01/10 20:24:25	offline	active	  
172.22.22.199	00:26:4a:18:81:a0		2011/01/09 11:12:07	2011/01/10 11:12:07	offline	active	  
172.22.23.102	00:0e:08:db:08:0a	phone103	2011/01/09 20:23:45	2011/01/09 22:23:45	online	active	 
172.22.22.200	00:1c:c0:51:a8:d8	tigas	n/a	n/a	online	static	 
172.22.22.201	00:19:3c:3c:02:1e	raid	n/a	n/a	offline	static	 
172.22.22.202	00:1e:37:8a:cc:43	t61p	n/a	n/a	online	static	 

2. By default, only **active** and **static** leases are shown. To view **expired** leases, click the **Show all configured leases** button:

Status: DHCP leases 

IP address	MAC address	Hostname	Start	End	Online	Lease Type	
172.22.23.197	90:84:0d:9d:fc:57	Matts-iPhone	2011/01/09 20:56:00	2011/01/10 20:56:00	online	active	 
172.22.23.199	00:1d:e0:a7:8e:c5	Thinkpad	2011/01/09 20:35:54	2011/01/09 22:35:54	offline	active	  
172.22.23.192	00:26:08:ae:b3:3a	Alexs-iPhone	2011/01/09 20:24:25	2011/01/10 20:24:25	offline	active	  
172.22.22.199	00:26:4a:18:81:a0		2011/01/09 11:12:07	2011/01/10 11:12:07	offline	active	  
172.22.22.102	90:84:0d:9d:fc:57		2011/01/02 15:53:30	2011/01/02 16:53:11	offline	expired	  
172.22.22.100	00:26:08:ae:b3:3a		2011/01/02 12:08:55	2011/01/02 16:48:18	offline	expired	  

How it works...

When configured as a DHCP server, pfSense hands out an IP address to any device that requests one. This page is often the first page to check when troubleshooting network connectivity problems with a device.

Adding a static DHCP mapping

If we see a device on the list that'd we'd always like to have the same IP address, we can add a static mapping for it by simply clicking the "plus" button.

Services: DHCP: Edit static mapping S L ?

Static DHCP Mapping

MAC address	<input type="text" value="90:84:0d:9d:fc:57"/> Copy my MAC address <small>Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx</small>
IP address	<input type="text"/> <small>If no IP address is given, one will be dynamically allocated from the pool.</small>
Hostname	<input type="text" value="Matts-iPhone"/> <small>Name of the host, without domain part.</small>
Description	<input type="text"/> <small>You may enter a description here for your reference (not parsed).</small>

Save Cancel

Sending a wake on LAN mapping

If we see a device that we want to send "magic packets" to, we can add a WOL mapping by simply clicking the **w** button:

Services: Wake on LAN: Edit ?

Edit WOL entry

Interface	PUB ▾ <small>Choose which interface this host is connected to.</small>
MAC address	<input type="text" value="90:84:0d:9d:fc:57"/> <small>Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx</small>
Description	<input type="text" value="Matts-iPhone"/> <small>You may enter a description here for your reference (not parsed).</small>

Save Cancel

See also

- ▶ The *Creating static DHCP mappings* recipe in *Chapter 2, Essential Services*













Managing services

This recipe describes how to manage the services running in pfSense.

How to do it...


1. Browse to **Status | Services**:













Status: Services ?

Service	Description	Status	
dnsmasq	DNS Forwarder	 Running	 
ntpd	NTP clock sync	 Running	 
dhcpcd	DHCP Service	 Running	 
miniupnpd	UPnP Service	 Running	 

2. To restart a service, click the **restart** button:


Status: Services ?












 miniupnpd has been restarted.
 Close

Service	Description	Status	
dnsmasq	DNS Forwarder	 Running	 
ntpd	NTP clock sync	 Running	 
dhcpcd	DHCP Service	 Running	 
miniupnpd	UPnP Service	 Running	 

3. To stop a service, click the **stop** button:


Status: Services ?













 miniupnpd has been stopped.
 Close

Service	Description	Status	
dnsmasq	DNS Forwarder	 Running	 
ntpd	NTP clock sync	 Running	 
dhcpcd	DHCP Service	 Running	 
miniupnpd	UPnP Service	 Stopped	

4. To start a service, click the **start** button:

Status: Services

 miniupnpd has been started. Close

Service	Description	Status	
dnsmasq	DNS Forwarder	 Running	 
ntpd	NTP clock sync	 Running	 
dhcpd	DHCP Service	 Running	 
miniupnpd	UPnP Service	 Running	 

How it works...

pfSense package management allows for services to be independently stopped and started. This is particularly helpful to administrators who can force a service to restart without taking down the entire system.

See also

- ▶ pfSense Service Status Documentation
http://doc.pfsense.org/index.php/Services_Status

Monitoring the packet filter with pflInfo

This recipe describes how to view pfSense's packet filter information.

How to do it...

1. Browse to **Diagnostics** | **pflInfo**:

Diagnostics: pfInfo

Status: Enabled for 7 days 07:02:29			Debug: Urgent		
Hostid: 0xd54c9328					
Checksum: 0x09f3c370c92d212bc6f153a78f8c73f6					
Interface Stats for em2			IPv4	IPv6	
Bytes In	45587928			0	
Bytes Out	247865172			96	
Packets In					
Passed	230792			0	
Blocked	402			0	
Packets Out					
Passed	598572			0	
Blocked	0			1	
State Table			Total	Rate	
current entries	2770				
searches	467273767			741.5/s	
inserts	3144108			5.0/s	
removals	3141338			5.0/s	
Source Tracking Table					
current entries	0				
searches	0			0.0/s	
inserts	0			0.0/s	
removals	0			0.0/s	
Counters					
match	3966931			6.3/s	

How it works...

System administrators will find the following information displayed about the packet filter:

- ▶ Interface statistics
- ▶ State table statistics
- ▶ Limits configuration
- ▶ Rule state
- ▶ Byte counters

See also

- ▶ PfSense pfInfo Documentation
http://doc.pfsense.org/index.php/Packet_Filter_Information

Monitoring traffic with pfTop

This recipe describes how to view the current traffic flow using the pfTop utility.

How to do it...

1. Browse to **Diagnostics** | **pfTop**:

Diagnostics: pfTop ?

Sort type:

pfTop: Up State 1-3267/3267, View: default, Order: source addr									
PR	D	SRC	DEST	STATE	AGE	EXP	PKTS	BYTES	
udp	I	0.0.0.0:68	255.255.255.255:67	0:1	13	47	1	328	
tcp	I	2.36.13.132:1136	172.22.22.202:51413	4:4	37236	50965	1471	858K	
tcp	O	2.36.13.132:1136	172.22.22.202:51413	4:4	37236	50965	1471	858K	
tcp	I	2.91.87.191:17433	172.22.22.202:51413	4:4	68396	19017	38	6176	
tcp	O	2.91.87.191:17433	172.22.22.202:51413	4:4	68396	19017	38	6176	
tcp	I	2.120.1.88:50219	172.22.22.202:51413	4:4	60538	26733	40	4060	
tcp	O	2.120.1.88:50219	172.22.22.202:51413	4:4	60538	26733	40	4060	
tcp	I	2.120.1.88:51778	172.22.22.202:51413	4:4	58973	28352	36	4498	
tcp	O	2.120.1.88:51778	172.22.22.202:51413	4:4	58973	28352	36	4498	
tcp	I	2.120.1.88:53374	172.22.22.202:51413	4:4	57429	29848	38	4375	

How it works...

System administrators can use the **pfTop** utility to monitor current bandwidth and traffic. The data displayed by this utility can be sorted by any of the following criteria:

- ▶ Bytes
- ▶ Age
- ▶ Destination
- ▶ Destination Port
- ▶ Expiration
- ▶ None
- ▶ Peak
- ▶ Packets
- ▶ Rate
- ▶ Size
- ▶ Source Port
- ▶ Source

See also

- ▶ pfSense Bandwidth Monitoring Documentation
http://doc.pfsense.org/index.php/How_can_I_monitor_bandwidth_usage%3F#pftop

Monitoring system activity

This recipe describes how to monitor system activity in pfSense.

How to do it...

1. Browse to **Diagnostics | System Activity**:

Diagnostics: System Activity

```

last pid: 6410; load averages:  0.14,  0.27,  0.16 up 7+07:24:08   22:03:31
106 processes: 2 running, 80 sleeping, 24 waiting

Mem: 45M Active, 41M Inact, 68M Wired, 396K Cache, 110M Buf, 827M Free
Swap:

  PID USERNAME PRI NICE  SIZE  RES STATE   TIME  WCPU COMMAND
    10 root      171 ki31    OK    8K RUN    166.3H 92.57% idle
    11 root      -68 -    OK   192K WAIT   178:51  0.98% {irq20: fxp0}
    11 root      -68 -    OK   192K WAIT   151:35  0.98% {irq265: em3:rx 0}
22730 root       48 0 34692K 15836K piperd    0:11  0.98% php
    11 root      -68 -    OK   192K WAIT    12:19  0.00% {irq266: em3:tx 0}
    11 root      -32 -    OK   192K WAIT    12:18  0.00% {swi4: clock}
    11 root      -64 -    OK   192K WAIT    10:50  0.00% {irq15: atal}
    13 root      -16 -    OK    8K -      10:13  0.00% yarrow
31177 root       44 0 3316K  1300K select   3:33  0.00% apinger
10765 root       76 20 3656K  1424K wait    3:22  0.00% sh
19205 root       44 0 3316K   888K piperd    3:14  0.00% logger
53022 nobody    44 0 5552K  2496K select   1:43  0.00% dnsmasq
12723 root       76 0 54692K 16456K accept   1:15  0.00% php
18890 root       44 0 11032K  8280K bpf     1:12  0.00% tcpdump
    0 root      -16 0    0K    112K sched    0:54  0.00% {swapper}
52249 dhcpd    44 0 7776K  4068K select    0:52  0.00% dhcpd
    2 root       -8 -    0K    8K -      0:47  0.00% g_event
    7 root      -16 -    0K    8K pftm    0:45  0.00% pfpurge

```

How it works...

Administrators can monitor the core system activity of pfSense, including the following resources:

- ▶ Last process ID (PID)
- ▶ Load averages
- ▶ Uptime
- ▶ Process statistics
- ▶ Memory statistics
- ▶ Swap statistics

See also

- ▶ pfSense System Activity Documentation
http://doc.pfsense.org/index.php/System_Activity

B

Determining our Hardware Requirements

This appendix covers the following topics:

- ▶ Determining our deployment scenario
- ▶ Determining our throughput requirements
- ▶ Determining our interface requirements
- ▶ Choosing the standard or embedded image
- ▶ Choosing a form factor

Introduction

Whether our environment is a home network consisting of two computers or a corporate data center comprised of hundreds of machines, it's essential to begin by determining exactly what we need from our firewall.

The versatility of pfSense presents us with a wide array of configuration options which, compared to other offerings, makes determining requirements a little more difficult and that much more important. The latest firewall product from Microsoft, for example, requires a dual-core processor, 2 GB of RAM, 2.5 GB of hard disk space, and the latest version of the Windows Server platform. In this case, we'd probably end up buying a new server, and that would be fine. We would be finished with our decision and we wouldn't need to read this chapter.

pfSense would run just fine on new hardware but as we'll see, pfSense offers numerous other alternatives to fit any environment's security needs.

Determining our deployment scenario


This recipe will determine which of the many pfSense deployment scenarios is right for our environment by analyzing our network diagram.

Getting ready

This recipe requires the use of our network diagram to understand how and where pfSense will fit into our environment. As an example we'll be using my own home network diagram. This diagram is a good example of a typical small-office environment (minus the video game consoles).

How to do it...

1. Let's analyze our network diagram:



2. In this small-office scenario, the firewall that we have diagrammed fits the definition of a perimeter firewall. This is the most common of all pfSense deployments.

How it works...

A **perimeter firewall** becomes the gatekeeper of all traffic flowing between interfaces. We will define firewall rules based on how we want that traffic to flow. A few common rules that most networks enforce are:

- ▶ **Allow all from LAN to WAN:** Allow users to get to the outside world so that they can surf the web, send e-mails, and so on.
- ▶ **Allow some from LAN to WAN:** A practice known as **egress filtering** involves limiting the types of traffic allowed to leave a network to ensure unauthorized or malicious traffic never leaves a network.
- ▶ **Block all from WAN to LAN:** Do not allow external users to get into our own private network.
- ▶ **Allow HTTP from LAN to DMZ:** Allow our internal users to access our company's webserver.
- ▶ **Allow HTTP from WAN to DMZ:** Allow external users to access our company's webserver.
- ▶ **Block all from DMZ to LAN:** Our DMZ is insecure since we're allowing external users to come in and access the web server. We want to protect ourselves by blocking any traffic that attempts to access our LAN from the DMZ.

pfSense also employs many advanced firewall features to accommodate the needs of more complex networks. pfSense is capable of:

- ▶ Supporting dozens of interfaces if necessary
- ▶ Handling multiple Internet connections, in case the primary Internet connection fails
- ▶ Fail-over protection, in case the primary firewall dies
- ▶ Load-balancing, to optimize network traffic by balancing demanding loads

There's more...

pfSense is highly flexible and can also be configured as any of the following devices. It's important to note that these roles are simply services that we will use within our perimeter firewall deployment, but larger environments may want to build these roles as separate machines to improve performance:

- ▶ **Router:** This is the second most common deployment of pfSense. A router determines a packet's destination and then sends it on its way, without applying any firewall rules.

- ▶ **VPN appliance:** A VPN server provides encrypted remote network connections. pfSense supports all the major virtual private networking protocols such as IPsec, PPTP, OpenVPN, and L2TP.
- ▶ **DHCP appliance:** A DHCP server assigns IP addresses to clients that request them.
- ▶ **DNS appliance:** A DNS server associates names with IP addresses. It's much easier to remember "google.com" than "173.194.33.104".
- ▶ **VoIP appliance:** **Voice over IP (VoIP)** is digital telephony, possible with pfSense using the FreeSWITCH package.
- ▶ **Sniffer appliance:** Sniffers analyze packets for patterns. This is often to detect and prevent traffic that attempts to exploit known vulnerabilities. pfSense utilizes the most widely deployed sniffer package in existence, Snort.
- ▶ **Wireless Access Point:** pfSense can be deployed strictly as a wireless access point.

pfSense can be configured with many more devices—pfSense being deployed as a special purpose appliance is only limited by the number of packages supported by the platform.



For more information, read through the PfSense online documentation:
Common Deployments

http://www.pfsense.org/index.php?option=com_content&task=view&id=71&Itemid=81

Determining our throughput requirements

This recipe will explain how to determine the throughput requirements, and subsequently the processing and memory requirements needed in our environment.

Getting ready

We'll want to prepare for determining our requirements by gathering the following information:

- ▶ Our Internet connection speed.
- ▶ Our network hardware speed. Will our network be capable of 10, 100, or 1000 Mbps speeds?
- ▶ What connection speeds will our different types of users be expecting?

How to do it...

1. Let's review the general throughput and feature guidelines (available at <http://pfsense.com/> at **Hardware | Selection & Sizing**):

Firewall throughput	Processing power required	Server hardware (PCI-X/PCI-e NICs)
10-20 Mbps	266-MHz CPU	No
21-50 Mbps	500-MHz CPU	No
51-200 Mbps	1-GHz CPU	No
201-500 Mbps	2-GHz CPU	Recommended
501+ Mbps	3-GHz CPU	Recommended

The following table defines any additional system requirements that would be necessary if deploying optional features:

Feature	Additional Requirements
VPN	A CPU's encrypted throughput is roughly 20 percent of its unencrypted throughput. If you have a 500-Mhz processor (~50 Mbps unencrypted) and you need more than 10 Mbps encrypted throughput, you're going to need a faster processor or a separate encryption card.
Captive portal	Environments with a larger number of captive portal users (100+) may need to bump their processing power slightly to achieve the same throughput.
Large state tables	The default state table size of 10,000 entries takes up 10 MB of RAM. Large environments with hundreds of thousands of entries will want to make sure they have the necessary memory available.
Squid Package	It is a package used for caching web content which requires extensive use of a hard disk with a large amount of storage. It is not for use with an embedded installation where writes to the compact flash card are kept to a minimum.
Snort Package	It is a packet sniffer/intrusion prevention and detection system (IPS/IDS). A minimum of 512 MB RAM is required.
NTop Package	A network traffic reporting tool. A minimum of 512 MB of RAM required.

2. Now, let's determine our own requirements:

- ❑ Our medium-sized business, *Any Company USA*, has 100 typical business users. Our network infrastructure consists of CAT5 cable and 100 Mbps switches. The majority of our traffic is web browsing, e-mails, and small file sharing. Our 100-Mbps Internet connection is ample, and our primary concern is being able to use what we're paying for.
- ❑ We want to provide VPN access for employees on the go, but we expect no more than a handful of VPN connections at any given time and throughput for these external users isn't a primary concern. Of the additional packages available to pfSense, we've decided we'd like to use the NTop package to help us analyze our traffic and identify problems.

- ❑ Lastly, given the money we're saving using the open source pfSense platform, we're going to build an additional fail-over firewall to comply with our organization's redundancy IT policy.
- 3. At this point we've identified our requirements as:
 - ❑ 1 Gbps network hardware (cables and switches)
 - ❑ Unencrypted throughput of 100 Mbps
 - ❑ Encrypted throughput (VPN) of 20 Mbps
 - ❑ 1-GHz CPU, 1-GB RAM
 - ❑ A second identical machine to be used as a failover

How it works...

Throughput is the amount of data that can be processed at any given time. We may have a 100 Mbps fiber-optic Internet connection, but if our firewall's hardware can only process 20 Mbps, then that's all we're going to get.

Firewall throughput is only a factor for traffic *passing through* the firewall. Internet traffic meets this requirement (LAN <| WAN), as would any traffic between our own networks (LAN <| DMZ). However, traffic between two machines on the same network, 2 PCs in our LAN for example, won't be bottlenecked by the firewall.

There's more...

It's important to remember that certain firewall features have their own hardware requirements. For example, VPN connections require additional processing power and the Squid web-caching package isn't suitable for an embedded compact flash disk installation.

List of available packages

Unfortunately, a current list of packages available to pfSense isn't maintained online. Once pfSense is installed, we can view available packages in the **System | Packages** menu.

See also

- ▶ See Available Packages in *Appendix A, Monitoring and Logging*
- ▶ PfSense Official Documentation: Minimum Requirements
http://www.pfsense.org/index.php?option=com_content&task=view&id=45&Itemid=48
- ▶ PfSense Official Documentation: Selection & Sizing
http://www.pfsense.org/index.php?option=com_content&task=view&id=52&Itemid=49

Determining our interface requirements


This recipe will help us determine our interface requirements by analyzing our network design.

Getting ready

This recipe requires the analysis of our network diagram to understand how many interfaces our network will require. As an example, we'll be using my own home network diagram, which is a good example of a typical small office environment.

How to do it...

1. Let's analyze our network diagram:



2. We can see that our environment consists of four separate interfaces:
- ❑ **WAN (Wide Area Network):** The Internet.
 - ❑ **LAN (Local Area Network):** Our primary internal network.
 - ❑ **DMZ (Demilitarized Zone):** Our internal network we allow external access to. Web servers, e-mail servers, and any other externally accessible devices belong to this interface.
 - ❑ **WiFi (Wireless Guest Network):** We've created this network for the convenience of our guests. They can connect with an easy-to-remember password (or perhaps no password at all) and surf the Web. We consider this interface insecure and treat it as such. We will define rules so that it has no access to our other interfaces.

It's apparent that our firewall requires four **Network Interface Cards (NIC)**.



Alternatively, the preceding diagram could be accomplished with two interfaces (WAN and LAN) and two VLANs (DMZ and WIFI).

How it works...

A firewall requires a separate NIC for every interface it hopes to support. This ensures a physical separation of network traffic. All inter-network traffic is forced to pass through the firewall where our rules will be applied and enforced. For that reason, a firewall requires a minimum of two NICs to function properly; one for internal traffic and one for external traffic. Each subsequent optional interface will require yet another NIC, which can be added at any time.

There's more...

Typically, an NIC will have a single Ethernet port. However, some NICs may have two, four, or even more Ethernet ports on a single card. Our firewall in the preceding scenario could have four single-port NICs or a single four-port network interface card. Either way, it works.

Single-port NIC



Four-port NIC



pfSense 2.0: Minimum interface requirements

New to the latest version of PfSense is a single interface minimum to install the system. This means that all interfaces are now optional, except for the WAN. This allows for more flexibility while building or upgrading the system, but a proper firewall still requires a minimum of two.

Choosing a standard or embedded Image

This recipe describes how to make the choice of using the standard or embedded version of pfSense.

Getting ready

Every standard feature of pfSense is supported on both the standard and embedded platforms but certain packages are not. The Squid web-caching package, for example, requires extensive writing to disk and should not be run on a compact flash drive.

How to do it...

1. Let's review the package we've chosen to install:

NTop package: It is a traffic analysis tool. It requires a minimum of 512 KB RAM, but has no restrictions on the storage type.

2. Based on this and the convenience of compact flash cards, we're going to install the embedded version of pfSense.

How it works...

The standard image is meant to be installed on a hard drive. The embedded version is meant to be installed on a compact flash drive. Compact flash drives only have a limited number of writes during their lifespan and the embedded version of pfSense is designed to limit writes to the disk for this very reason. That being said, each platform has some distinct advantages and disadvantages:

Platform	Pros	Cons
Standard	All packages and features are supported Large amount of cheap storage space	Entire drive must be overwritten (dual booting is not supported) Require larger power supply
Embedded	Fast access times Cards can be easily swapped (backup, upgrades, and so on) Requires little power Silent	CF cards have a limited number of writes Not all packages are supported

There's more...

The installation disk for the standard version of pfSense is also a Live CD. If you'd just like to try pfSense out without installing it to any machine, you can run it live from the CD. You can even save your configuration to a floppy disk or USB drive. However, not all features are available while running pfSense from the Live CD.

See also

- ▶ pfSense online documentation: Versions
http://www.pfsense.org/index.php?option=com_content&task=view&id=43&Itemid=44

Choosing a Form Factor

This recipe describes how to choose the best hardware configuration based on our firewall requirements.

Getting ready

It's easiest to choose a form factor if we've already decided on the rest of our prerequisites:

- ▶ Deployment scenario
- ▶ Throughput requirements
- ▶ Interface requirements
- ▶ Image platform

How to do it...

Evaluate the different types of form factors:

1. **Small form:** Energy-efficient, quiet (often silent), small foot print form factor.
2. **Desktop:** Standard desktop hardware. Easily upgradable and most people will have an older machine lying around that's perfectly suited for running pfSense.
3. **Server:** Larger or more complex environments may require server class hardware.

Consider if any of our requirements require special hardware. In our case, we need moderate throughput and aren't using any packages that require special hardware. Low-power consumption and silent operation is important to our small office, so we're opting for small form factor.

How it works...

The choice of form factor has more to do with our environment than our pfSense installation. Every environment will vary and form factors will differ. Thanks to the vast variety of computer hardware on the market, any deployment of pfSense is possible on any type of form factor. While most standard platforms are installed on desktops, and most embedded platforms on appliances, there's no reason they can't be swapped if we've equipped our hardware properly.

There's more...

There's no reason we can't use a laptop! If we have an old laptop lying around, it would probably make a great, although unusual, pfSense machine. The biggest obstacle we'd likely face is adding additional NICs, but a USB Ethernet Adapter ought to work, although they are never recommended for production systems.




As with all open-source projects, it's best to refer to the project's hardware compatibility list before adding new hardware.



Installing the embedded platform on a desktop/server/laptop

Some people really enjoy the convenience of running a system from a compact flash card. Testing a new version of pfSense, or reverting back to a backup, is as easy as swapping CF cards. Most desktops don't come with a CF card reader installed, but there are plenty of adapters to choose from:



Installing the standard platform on an appliance

Of all the different installation scenarios, installing the standard version on an appliance equipped with a hard drive can be the most challenging. Appliances are meant to be small, so if they've already fit a hard drive in there you can bet there won't be an optical drive. Secondly, most appliances don't have built-in video-out which means another means of connection (usually serial or USB) is required.

We'll have to refer to our manufacturer's documentation if we find ourselves in this situation. There isn't much documentation available on the subject, but the pfSense guys have posted instructions on how to install the standard image on a Netgate Hamakua at http://doc.pfsense.org/index.php/Full_install_on_Netgate_Hamakua.

See also

- ▶ pfSense official documentation: Recommended Vendors

http://www.pfsense.org/index.php?option=com_content&task=view&id=44&Itemid=50

Index

Symbols

1:1 NAT rule

configuring 103

1:1 NAT rule configuration

about 103-105

working 105

A

advanced features, firewall rule

Ackqueue/Queue setting 60, 61

advanced options setting 55

Diffserv Code Point setting 58, 59

Gateway setting 60

In/Out setting 60

Layer7 setting 61

No XMLRPC Sync setting 60

Schedule setting 60

Source OS setting 58

State Type setting 60

TCP Flags setting 59

alias

about 45

bulk importing 50

creating 46

deleting 50

editing 50

host alias 46

modifying 47

network alias 48

Open VPN user 48, 49

port alias 48

URL alias 49

URL Table alias 49

using 49, 50

using, example 47

working 46

Allow all from LAN to WAN 217

Allow HTTP from LAN to DMZ 217

Allow HTTP from WAN to DMZ 217

Allow some from LAN to WAN 217

alternate DNS Servers

DNS Forwarder, using 36

specifying, steps 35

starting with 35

WAN DNS Servers, using 36

working 36

appliance

standard platform, installing 226

authorized RSA keys

about 19, 21

generating 19, 20

generating, PuTTY used 20, 21

working 21

Automated Configuration Backup Documentation

URL 184

automatic configuration file backup

configuring 183, 184

B

Block all from DMZ to LAN 217

Block all from WAN to LAN 217

C

captive portal

creating, steps 124, 125

pages, customizing 127

starting with 124

working 126

CARP firewall failover

configuring 149-156

starting 149

- steps 150-154
- working 155

Configuration Backup/Restore Documentation

- URL 180, 183

configuration file

- backing up 178-180
- restoring 180-183

configuring

- DHCP relay 32
- DHCP Server 28
- DNS Forwarder 36
- dynamic DNS 42
- L2TP VPN service 74
- multi-WAN load balancing 137
- OpenVPN service 80
- PPTP VPN service 86
- standalone DHCP/DNS Server 39

current traffic

- monitoring 194

D

deployment scenario

- determining 216-218

desktop

- embedded platform, installing 226

DHCP appliance 218

DHCP leases

- viewing 206, 207

DHCP relay configuration

- about 32
- Agent ID, appending to requests 34
- Circuit ID, appending to requests 34
- Relay Requests to the WAN DHCP Server 34
- starting with 33
- steps 33
- working 34

DHCP Server configuration

- about 29
- additional BOOTP/DHCP options 30
- default lease time 30
- DNS Servers 29
- domain name 29
- Dynamic DNS 30
- Failover Peer IP 30
- gateway 29
- maximum lease time 30
- starting with 28

- Static ARP 30
- steps 28
- unknown clients, denying 29
- working 29

Diffserv 58

DMZ (Demilitarized Zone) 222

DNS appliance 218

DNS Forwarder configuration

- starting with 36
- steps 37, 38
- working 38

dynamic DNS configuration

- alternative service specifying, RFC 2136 used 44
- pre-configured service types 43
- starting with 42
- steps 42
- working 43

E

embedded image

- selecting 223, 224

embedded platform

- installing, on desktop 226
- installing, on laptop 226
- installing, on server 226

external logging. See Syslog

external syslog server

- configuring 199
- syslog service, running in Linux/Mac OS 200
- syslog service, running in Windows 200

F

failover 129

firewall rule

- advanced features 58
- configuring 57
- creating 55
- duplicating 58
- ordering 58
- starting with 55
- working 57

Firmware Update Documentation

- URL 189

form factor

- selecting 224, 225

G

gateway

- creating, steps 111, 112
- Gateway Groups 112
- starting with 111
- working 112

General Setup, pfSense

- basic settings, applying 6, 7

H

High Latency 138

I

interfaces

- assigning 8-10
- identifying 8-10
- minimum requisites 223
- requisites, determining 221, 222

interfaces, bridging

- steps 120
- use 121

Internet Service Provider (ISP) 11

IPsec VPN tunnel

- creating, steps 72-74
- starting with 72
- working 74

K

Kiwi Syslog Server

- URL 174

L

L2TP VPN service

- configuring, steps 74, 76
- connecting, from Windows 7 client 76-80
- starting with 74
- working 76

LAN interface

- about 222
- configuring 13, 14

laptop

- embedded platform, installing 226

load balancing 129

Local Area Network. *See* LAN interface

Log Settings Documentation

- URL 174

Log Viewer

- URL 174

M

Member Down 138

multiple WAN interfaces

- configuring 130-134
- starting 130
- steps 130, 134
- working 134

multi-WAN failover

- starting 138
- steps 138-141
- working 141

multi-WAN load balancing

- configuring 135-141
- starting 135
- steps 135, 136
- working 137

multi-WAN load balancing, configuring 137

N

NAT-PMP

- enabling 165-167

NAT port forward rule

- configuring, options 53
- creating 51
- redirecting 54
- starting with 51
- working 52

Network Interface Cards (NIC) 222

NTPD Documentation

- URL 169

O

OLSR

- enabling 158, 159

OpenNTPD

- enabling 168

OpenNTPD.org

- URL 169

OpenVPN

- about 71
- configuring 80
- OpenVPN configuration**
 - encryption algorithm, choosing 84
 - OpenVPN Client Export 85
 - steps 80-84
 - working 84
- Optimized Link State Routing Protocol.** *See* **OLSR**
- optional interfaces**
 - configuring, steps 15, 16
- Outbound NAT Rule**
 - creating, steps 106-109
 - starting steps 106
 - working 110

P

- packet filter**
 - monitoring, with pfInfo 210, 211
- Packet Loss 138**
- perimeter firewall 217**
- pfInfo**
 - packet filter, monitoring 210, 211
- pfSense**
 - about 5
 - alternate DNS Servers, specifying 35
 - authorized RSA keys, generating 19, 20
 - automatic configuration file backup, configuring 183, 184
 - captive portal 126
 - CARP firewall failover, configuring 149-156
 - configuration file, backing up 178-180
 - configuration file, restoring 180-183
 - current traffic, monitoring 194
 - deployment scenario, determining 216-218
 - DHCP leases, viewing 206, 207
 - embedded image, selecting 223, 224
 - essential services 27
 - external logging (syslog server), enabling 172
 - external syslog server, configuring 199, 200
 - form factor, selecting 224, 225
 - gateway, creating 110
 - General Setup, basic settings applying 6, 7
 - interface requirements, determining 221, 222
 - interfaces, assigning 8-10
 - interfaces, identifying 8-10

- LAN interface, configuring 13, 14
- multiple WAN interfaces, configuring 130-134
- multi-WAN load balancing, configuring 135-141
- NAT-PMP, enabling 165-167
- OLSR, enabling 158, 159
- OpenNTPD, enabling 168
- packet filter, monitoring with pfInfo 210, 211
- pfSense firmware, updating 185-187
- Ping, using 174, 175
- PPPoE, enabling 160-162
- RIP, enabling 162
- RRD graphs, viewing 201-206
- services, managing 208
- SMTP e-mail notifications, configuring 195, 196
- SNMP, enabling 163-165
- SSH RSA key authentication, configuring 22
- standard image, selecting 223, 224
- static DHCP mappings, adding 30
- status dashboard, customizing 191-193
- syslog service in Windows, running 200
- system activity, monitoring 213, 214
- system logs, viewing 196, 197
- throughput requirements, determining 218-220
- traceroute, using 176, 177
- traffic, monitoring with pfTop 211, 213
- UPnP, enabling 165-167
- virtual IP addresses, types 98
- Wake On LAN (WOL), enabling 169-172
- WAN Interface, configuring 10, 12
- web server failover, configuring 145-149
- web Server load balancer, configuring 142-145
- pfSense firmware**
 - updating 185-187
- PfSense Official Documentation**
 - URL 220
- PfSense online documentation**
 - URL 218, 224
- pfsync 149**
- pfTop**
 - traffic, monitoring with 211, 213
- Ping**
 - using 174, 175
- Point-to-Point Protocol over Ethernet.** *See* **PPPoE**

Point-to-Point Protocol (PPP) 160

PPPoE

enabling 160-162

PPTP VPN service

configuring 86

working 88

PPTP VPN service, working

connecting, from Apple Mac OSX Client 94, 95

connecting, from Ubuntu 10.10 client 91, 92

connecting, from Windows 7 client 88-91

Premium Portal

URL 184

PuTTYGen tool 19

Q

Quality of Service (QoS). *See* **Traffic Shaping**
Quality tab 204

R

RDP 65

red textbox 49

Redundant WAN interfaces (multi-WAN) 129

Remote Desktop Protocol. *See* **RDP**

remote desktop access

security, tightening 68, 69

starting with 65

steps 66

working 68

RIP

enabling 162

router 217

Routing Information Protocol. *See* **RIP**

RRD graphs

custom 206

packets 204

quality 204

system 202

traffic 203

viewing 201-203

VPN 205

S

schedule

creating 61, 62

starting with 61

status, determining 63

working 63

Secure Shell (SSH)

accessing 23, 24

enabling 18

enabling, steps 19

working 18

server

embedded platform, installing 226

services

managing 208-210

Simple Network Management Protocol. *See*

SNMP

SMTP e-mail notifications

configuring 195, 196

Sniffer appliance 218

SNMP

enabling 163-165

SNMP Daemon documentation

URL 165

SSH RSA key authentication

about 22

configuring 22, 23

standalone DHCP/DNS Server configuration

DHCP Leases registration, in DNS Forwarder 41

steps 39, 40, 41

working 41

standard image

selecting 223, 224

standard platform

installing, on appliance 226

static DHCP mappings

adding 208

creating, steps 31, 32

starting with 31

viewing 32

working 32

static routes

creating, steps 113

starting with 113

working 114

status dashboard

customizing 191, 193

Syslog

enabling 172, 174

Syslog Article

URL 174

system activity

monitoring 213, 214

System Dashboard

shortcut 189

system logs

dynamic firewall log view 198

normal firewall log view 198

summary firewall log view 198

viewing 196, 197

T

throughput

requisites, determining 218-220

Traceroute Article

URL 177

Traceroute Documentation

URL 177

traffic

monitoring, with pfTop 211, 213

Traffic-Shaping

configuring 115

Traffic-Shaping configuration

starting with 115

steps 115-118

working 119

U

UPnP

enabling 165-167

UPnP Documentation

URL 168

V

virtual IP

CARP 99

CARP, configuring 100, 101

creating, steps 98

IP Alias 100

IP Alias, configuring 102, 103

Other 100

Proxy ARP 99

Proxy ARP, configuring 101, 102

starting with 98

working 99

Virtual LAN

creating, steps 122, 123

starting with 122

working 123

Virtual Private Networking. *See* VPN

VoIP appliance

Voice over IP (VoIP) 218

VPN

about 71

OpenVPN 71

VPN appliance 218

W

Wake All button 172

Wake-on-LAN Article

URL 172

Wake on LAN Documentation

URL 172

wake on LAN mapping

sending 208

Wake On LAN (WOL)

enabling 169-172

WAN Interface

configuring 10, 12

WAN (Wide Area Network) 222

web server failover

configuring 145-149

starting 146

steps 146, 148

working 149

web Server load balancer

configuring 142-145

starting 142

steps 142-144

working 145

Wide Area Network. *See* WAN interface

WiFi (Wireless Guest Network) 222

Wikipedia OpenNTPD Article

URL 169

Wireless Access Point 218

Z

ZoneEdit 43